



Stamping (PLOSSYS netdome, pdfstamp)

User Manual

Version 1.0.5

2023-10-24

SEAL Systems

Copyright

This document and all its parts are protected by copyright. Their use without prior written consent by SEAL Systems is prohibited and subject to prosecution. In particular, this applies to reproduction, translation, microfilming and the storing and processing in electronic systems.

Customers that currently own a valid SEAL Systems software license for the product(s) described within the contents of this document, may freely distribute this documentation in electronic form (i. e. CD/File Server or Intranet) for internal usage only.

All product names mentioned are the registered trademarks of the associated companies.

Copyright 2023

SEAL Systems AG
Lohmühlweg 4
D-91341 Röttenbach
Germany

Contents

| | |
|--|-----------|
| 1 Introduction..... | 7 |
| Conventions in this Documentation | 8 |
| Overview of Contents | 9 |
| | |
| Description..... | 11 |
| 2 General..... | 13 |
| 2.1 Stamp Programs and Configuration..... | 14 |
| 2.2 stamp types | 16 |
| 2.3 Stamp Texts | 17 |
| 2.4 Graphic Stamp | 19 |
| 2.5 Requirements | 20 |
| 3 Stamp Configuration | 21 |
| Configure a Text Stamp | 22 |
| Configure a Graphic Stamp..... | 23 |
| Configure the Reference Point of a Stamp Box | 24 |
| Configure an Opaque Stamp | 27 |
| Configure a Transparent Colored Stamp | 28 |
| Configure a Transparent Gray Stamp | 29 |
| Configure a Gray-Simulated Stamp | 30 |
| Configure a Watermark | 31 |
| Configure the Stamp Background..... | 32 |
| Configure an Invisible Stamp | 34 |
| Draw a Frame Around the Stamp Box | 36 |
| Rotate a Stamp Box | 38 |
| Configure the Pages to Be Stamped | 39 |
| Preset the Stamp Text | 40 |
| Align a Stamp Text to the Stamp Box | 41 |
| Group Stamp Texts | 43 |
| Configure the Repetition of a Stamp | 44 |
| Configure the Character Width and Spacing | 46 |
| 4 PLOSSYS netdome - Further Configuration and Operations | 47 |
| Stamp a Document..... | 48 |
| Stamp Over All Output Queues | 49 |
| Queue-Specific Stamp | 50 |
| Job-Specific Stamp..... | 51 |
| Pass a Stamp Text via a Header | 53 |
| Use a Variable in a Stamp Text | 54 |
| Rotate and/or Scale the Stamps with the Document..... | 55 |
| Stamp Only the First Page | 56 |
| Stamp the Front and Back Sides Differently..... | 57 |
| Relate Pages to Collection Set | 58 |
| Pass a Graphic File With a Job | 59 |
| Use a Variable in a GKS Metafile | 60 |
| Apply a Flagpage Onto a Document | 61 |
| 5 pdfstamp/pdfstampht - Further Configuration and Operations..... | 62 |
| Stamp a Document..... | 63 |
| Pass a Stamp Text via a Stamp Text File | 64 |
| Pass a Stamp Text via a Header | 65 |
| Specify a Stamp Text Directly | 66 |

| | |
|--|-----------|
| Use a Variable in a Stamp Text | 67 |
| Change the Displayed Page Number..... | 69 |
| Specify the Pages to Be Stamped..... | 70 |
| Keep PDF/A in the Output File | 71 |
| Mark a Stamp..... | 72 |
| Delete a Stamp..... | 73 |
| Generate a Stamp As PDF Annotation | 74 |
| Reuse the Temporary Stamp File | 75 |
| Apply a Flagpage Onto a Document | 76 |
| Configure Format-Specific Stamps..... | 78 |
| 6 Stamping Using a Stamp Template..... | 80 |
| Generate a Stamp Template | 81 |
| Stamp a Document | 82 |
| Position the Stamp Template on the Document | 83 |
| Select Pages From the Stamp Template | 84 |
| Specify the Pages to Be Stamped..... | 85 |
| Apply the Stamp Template As Watermark | 86 |
| Keep PDF/A in the Output File | 87 |
| Replace a Text in the Stamp Template | 88 |
| Reference | 89 |
| 7 Parameter of pdfstamp/pdfstampht - Reference | 91 |
| -af <binary> Properties of the PDF Annotation | 94 |
| -d <string> Delete a Stamp | 95 |
| -da <string> Delete an Adobe Stamp | 96 |
| -db <string> PDF Configuration File | 97 |
| -f <string> Input File..... | 98 |
| -forcepdfa Keep PDF/A in the Output File | 99 |
| -fp <string> Flagpage Configuration File | 100 |
| -fptxt<n> <string> Flagpage Texts..... | 101 |
| -graystamp <enumeration> Display of the Gray Stamps | 102 |
| -h Output the Usage | 103 |
| -hed <string> Header with Stamp Texts..... | 104 |
| -i <string> Page Configuration File | 105 |
| -k <string> Text to Be Replaced in the Stamp Template..... | 106 |
| -keep Do Not Delete Temporary Stamp Files | 107 |
| -ma Generate the Stamp As a PDF Annotation..... | 108 |
| -nopdfa Do No Force PDF/A..... | 109 |
| -o <string> Output File | 110 |
| -off <string> Offset of the Stamp Template | 111 |
| -p <enumeration> Pages to Be Stamped | 112 |
| -pos <string> Position of the Stamp Template..... | 113 |
| -pst <enumeration> Page From the Stamp Template | 114 |
| -rec Stamp Embedded Files Recursively | 115 |
| -setimagemask Change the White Background to Transparent | 116 |
| -setuu <float> UserUnit | 117 |
| -startpagecount <integer> Start of the Page Numbering | 118 |
| -sti <string> Mark a Stamp | 119 |
| -stp <string> Stamp Layout File or Stamp Template | 120 |
| -t <string> New Text for the Stamp Template | 121 |
| -t<n> <string> Stamp Text..... | 122 |

| | |
|---|------------|
| -totalpagecount <integer> Total Page Number..... | 123 |
| -txt <string> Stamp Text File..... | 124 |
| -uselogicalpage Consider startpagecount | 125 |
| -usepdfaswatermark Stamp As Watermark | 126 |
| -x <float> Width of the Stamp Template | 127 |
| -y <float> Height of the Stamp Template | 128 |
| 8 Configuration - Reference | 129 |
| 8.1 Stamp Layout File (.stp)..... | 130 |
| Items Without Section | 131 |
| [STAMP_DEFINITION] Section | 132 |
| [text] Section | 133 |
| [box] Section | 137 |
| [SIZE_DEFINITIONS] Section | 145 |
| Example of the Stamp Layout File | 147 |
| 8.2 PDF Configuration File (.db) | 149 |
| Items of the PDF Configuration File..... | 150 |
| Example of the PDF Configuration File | 154 |
| 8.3 Flagpage Configuration | 155 |
| Flagpage Configuration Settings..... | 156 |
| Example of the Flagpage Configuration Settings..... | 160 |
| Appendix A Examples of the Stamp Layout File | 161 |
| Colored Graphic Stamp Top Left | 162 |
| Red Text Stamp Across the Document | 164 |
| Transparent, Two-Line Text Stamp Bottom Right | 166 |
| Gray Text Stamp Center | 168 |
| Graphic Stamp As Watermark With Repetition..... | 170 |
| Stamp Mirrored Top Center | 172 |
| Bibliography..... | 174 |
| Terminology..... | 175 |
| Abbreviations..... | 176 |
| Index..... | 177 |

1 Introduction

This documentation describes the configuration of the stamps in PLOSSYS netdome and the PDF Tools pdfstamp/pdfstamphft.

purpose

This documentation is intended for users who want to configure stamps for PLOSSYS netdome or configure and use the PDF Tools pdfstamp/pdfstamphft.

target group

This chapter deals with the following topics:

in this chapter

| Topic | Page |
|-----------------------------------|------|
| Conventions in this Documentation | 8 |
| Overview of Contents | 9 |

Conventions in this Documentation

path specification

The path information given in this manual is relative to the installation directory of pdfstamp/pdfstampHFT and PLOSSYS netdome. The path information is indicated in Windows notation only in most cases. This corresponds to the UNIX directory structures unless noted otherwise.

typography

The following table lists the typographical conventions employed in this documentation.

| Typographical Convention | Meaning |
|--------------------------|---|
| Consolas | File names, paths, commands, menu items, keywords, special values, short scripts and examples |
| <i>Consolas italic</i> | Parameters; variables that have to be replaced by current values |
| Consolas small | More extensive scripts and examples |

Overview of Contents

This documentation has two parts: a description and a reference. The first part describes the functionality and the installation process using figures, step-by-step-procedures and explanatory texts. The second part serves as a detailed reference guide, containing configuration settings, keywords etcetera.

The description deals with the following topics:

Chapter 2, *General*, page 13, provides an introduction into the different ways how documents can be stamped at SEAL Systems, describes the basic terms and lists the requirements.

Chapter 5, *pdfstamp/pdfstamphft - Further Configuration and Operations*, page 62, explains the configuration steps that are identical for all ways of stamping.

Chapter 5, *pdfstamp/pdfstamphft - Further Configuration and Operations*, page 62, explains the additional configuration steps and actions available for the stamping via PLOSSYS netdome.

Chapter 5, *pdfstamp/pdfstamphft - Further Configuration and Operations*, page 62, explains the additional configuration steps and actions available for the stamping with pdfstamp/pdfstamphft.

Chapter 6, *Stamping Using a Stamp Template*, page 80, explains configuration steps for the stamping using a stamp template.

The reference contains the following chapters:

- Chapter 7, *Parameter of pdfstamp/pdfstamphft - Reference*, page 91, lists the command line parameters of pdfstamp/pdfstamphft.
- Chapter 8, *Configuration - Reference*, page 129, lists the settings in the different configuration files.

Appendix A, *Examples of the Stamp Layout File*, page 161, provides some examples for the configuration of stamps.

At the end of the documentation, a bibliography, terminology list, abbreviation list and index are included.


structure

description

reference

appendix

directories



Description

2 General

This chapter deals with the following topics:

in this chapter

| Topic | Page |
|----------------------------------|------|
| Stamp Programs and Configuration | 14 |
| stamp types | 16 |
| Stamp Texts | 17 |
| Graphic Stamp | 19 |
| Requirements | 20 |

2.1 Stamp Programs and Configuration

| | |
|---|--|
| programs | This documentation describes how to stamp with the following programs from SEAL Systems: <ul style="list-style-type: none">• PLOSSYS netdome• pdfstamp/pdfstamphft |
| Stamp Configuration | Basically, the configuration of the stamps is identical for the programs. Differences will be indicated at the correspondent situations. |
| stamp layout file | In the stamp layout file, you configure the layout of the stamp boxes and texts, for example, the size and the color, and the position of the stamp. → <i>Stamp Layout File (.stp)</i> , page 130 |
| stamp template | pdfstamp/pdfstamphft can also stamp a PDF file by means of another PDF file, a stamp template. In this case, a stamp layout file and stamp texts are not required. |
| PDF configuration file | The PDF configuration file specifies how the PDF output file will be generated. → <i>PDF Configuration File (.db)</i> , page 149 |
| pdfstamp/ pdfstamphft | pdfstamphft is the HFT variant of pdfstamp. |
| PLOSSYS netdome | PLOSSYS netdome always uses the HFT method. |
| background knowledge - HFT | HFT is a new method for calling functions whereby the Adobe Library is initialized using a different way. HFT is the seminal way and supports the automatic repairing as Adobe Acrobat Reader. PDF files with XFA can be processed with HFT. The "disadvantage" of HFT is that the protection mechanism are evaluated so that a document that is protected against changes can no longer be stamped before output. |
|  hint - stamp editor | As an alternative to the manual changing of the configuration files, you can configure the stamps by using the graphical user interface, Stamp Editor, from SEAL Systems. |

To be continued

Stamp Programs and Configuration, Continuation

With `pdfstamp/pdfstamphft`, you can configure up to 256 stamp boxes and texts.

number of stamps

With PLOSSYS netdome, the maximum of stamp boxes and texts is specified in the `PLS_STAMP_MAX` environment variable. This will be set when starting PLOSSYS netdome. Default is 100 stamps.

With the `tiffstamp` program from SEAL Systems, you can stamp TIFF files. For more information, refer to [TIFFSTAMP_TEC].

TIFF

2.2 stamp types

Stamp A stamp is a text or a graphic that is applied onto an existent document.

watermark A watermark is a stamp that is applied behind the document.

stamp types The following stamp types are supported:

- A „normal“, opaque stamp hides the contents of the document.
 - A transparent colored stamp hides the contents of the document but the colors are transparent so that you can see the contents through the stamp.
 - A transparent gray stamp hides the contents of the document but the gray-scales are transparent so that you can see the contents through the stamp.
 - A gray-simulated stamp hides the contents of the document. The gray-scales and colors are simulated by Black and White.
 - A real invisible stamp is invisible on all backgrounds but you can search for the text, for example.
-

flagpage In contrast to the other stamps, the flagpage may be output outside the document as well.

2.3 Stamp Texts

You can specify the texts for the text stamps in PLOSSYS netdome via the following ways:

- *Pass a Stamp Text via a Header*, page 65
- *Preset the Stamp Text*, page 40


PLOSSYS netdome

You can specify the texts for the text stamps in pdfstamp/pdfstamphft via the following ways:

- *Specify a Stamp Text Directly*, page 66
- *Pass a Stamp Text via a Stamp Text File*, page 64
- *Pass a Stamp Text via a Header*, page 65
- *Preset the Stamp Text*, page 40

pdfstamp/
pdfstamphft

The available ways for specifying the stamp texts may be combined. The texts specified with `-tn` take priority to the texts that are passed in the header with stamp texts and in the stamp text file. The default texts in the stamp layout file have the lowest priority.



A text stamp may contain 256 characters.

text length

For multiline stamp texts, you configure an extra stamp text for each line and assign these to the same stamp box.

- *Group Stamp Texts*, page 43

multiline

As of version 3.83 of pdfstamp/pdfstamphft, you can specify a line break with `\n` or `\r` in the stamp text. In order that these strings are handled as line breaks, set `TX_LINEBREAK` to `Y` in the stamp text file.

line break

Via `BO_WIDTH`, the maximum width of the stamp is specified. The line is broken at the word boundary. The value of `BO_HEIGHT` is adjusted accordingly. The line distance is specified via the `TX_LINEDISTANCE` option. If the text is wider than `BO_WIDTH` after the line break, the text size will be reduced if `BO_ADAPT_TEXT_TO_FRAME` has been set to `Y`. Otherwise, the text goes beyond the width specified by `BO_WIDTH` and `BO_WIDTH` is increased accordingly.

size with line
break

The stamps may contain variables which are replaced during stamping.

variables

To be continued

Stamp Texts, Continuation

Unicode

In order to generate stamp texts containing Unicode characters, the following environment variables must be set:

- `SEALFONTS=%PLSTOOLS%\fonts`
- `SEAL_DEFAULTCODEPAGE=UTF8`

The font used in the stamps must be Unicode-enabled, for example, -30001.

2.4 Graphic Stamp

A graphic stamp is a graphic that is applied onto the document.

graphic stamp

With PLOSSYS netdome, GKS metafiles can be used as graphic stamps.

PLOSSYS net-dome

With pdfstamp/pdfstamphft, GKS metafiles and JPEG files can be used as graphic stamps. Additionally, pdfstamp/pdfstamphft can stamp PDF files as stamp templates.

pdfstamp/
pdfstamphft

2.5 Requirements

pdfstamp/
pdfstamphft

pdfstamp and pdfstamphft belong to the PDF Tools from SEAL Systems.

 reference

The other PDF Tools and the general settings and information concerning the PDF Tools are described in [PDF_TOOLS].

3 Stamp Configuration

This chapter describes the configuration in the stamp layout file which is used both by PLOSSYS netdome and pdfstamp/pdfstamphft:

in this chapter

| Topic | Page |
|--|------|
| Configure a Text Stamp | 22 |
| Configure a Graphic Stamp | 23 |
| Configure the Reference Point of a Stamp Box | 24 |
| Configure an Opaque Stamp | 27 |
| Configure a Transparent Colored Stamp | 28 |
| Configure a Transparent Gray Stamp | 29 |
| Configure a Gray-Simulated Stamp | 30 |
| Configure a Watermark | 31 |
| Configure the Stamp Background | 32 |
| Configure an Invisible Stamp | 34 |
| Draw a Frame Around the Stamp Box | 36 |
| Rotate a Stamp Box | 38 |
| Configure the Pages to Be Stamped | 39 |
| Preset the Stamp Text | 40 |
| Align a Stamp Text to the Stamp Box | 41 |
| Group Stamp Texts | 43 |
| Configure the Repetition of a Stamp | 44 |
| Configure the Character Width and Spacing | 46 |

In Appendix A, *Examples of the Stamp Layout File*, page 161, you will find some examples of the configuration in the stamp layout file.



Configure a Text Stamp


instructions

This way you configure a text stamp:

| Step | Action |
|------|---|
| 1 | Configure the properties of the stamp box in the section for the stamp box: [box] |
| 2 | Configure the properties of the stamp text in the section for the stamp text: [text] |
| 3 | In the [STAMP_DEFINITION] section, specify the section names of the stamp text and the stamp box: [STAMP_DEFINITION] BOX_DEFINITIONS box TEXT_DEFINITIONS text |
| 4 | In the section for the stamp box, specify the stamp text as contents: [box] BO_CONTENTS text |



If the defaults are valid for all items of a stamp text, the correspondent [text] section can be empty but it must exist.




The Released text stamp is applied onto the document:

Extract of the stamp layout file:

```
[STAMP_DEFINITION]
  TEXT_DEFINITIONS      Text_0
  BOX_DEFINITIONS       Box_0

[Text_0]
  ...
    TX_TEXT              "Released"
  ...

[Box_0]
  ...
    BO_CONTENTS          Text_0
  ...
```



Configure a Graphic Stamp

With PLOSSYS netdome, the graphic file to be stamped on all jobs of a output queue is stored in the %PLSPLT% directory.

requirement

With pdfstamp/pdfstamphft, the graphic file is stored in the directory of the stamp layout file.

This is how you configure a graphic stamp:

instructions


| Step | Action |
|------|---|
| 1 | Configure the properties of the stamp box in the section for the stamp box: [box] |
| 2 | In the [STAMP_DEFINITION] section, specify the section name of the stamp box: [STAMP_DEFINITION] BOX_DEFINITIONS box |
| 3 | In the section for the stamp box, specify the graphic file: [box] BO_FRAME graphic ⚠ Caution - pdfstamp/pdfstamphft: With pdfstamp/pdfstamphft, deactivate the BO_CONTENTS item in the section for the stamp box in order that the BO_FRAME item is used. [box] # BO_CONTENTS ... |

The seal_logo.met graphic stamp is applied onto the document:



Extract of the stamp layout file:

```
[STAMP_DEFINITION]
  BOX_DEFINITIONS      Box_0
[Box_0]
...
  BO_FRAME            seal_logo.met
...
```





Configure the Reference Point of a Stamp Box

reference point
The position of a stamp box orient itself on the reference point which is relative to the border of the document or the printable area.

requirement
The text or graphic stamp has been configured:
→ *Configure a Text Stamp*, page 22
→ *Configure a Graphic Stamp*, page 23

instructions
This is how you configure the reference point of a stamp box:


| Step | Action |
|------|---|
| 1 | <p>In the section for the stamp box, configure where the reference point of the stamp box is to be located corresponding to the document's horizontal:</p> $[box] \text{BO_ALIGNMENT_HOR } align$  |
| 2 | <p>In the section for the stamp box, configure where the reference point of the stamp box is to be located corresponding to the document's vertical:</p> $[box] \text{BO_ALIGNMENT_VER } align$  |

..... *To be continued*

Configure the Reference Point of a Stamp Box, Continuation


This is how you configure the reference point of a stamp box, continuation:

instructions,
cont'd

| Step | Action |
|------|---|
| 3 | <p>In the section for the stamp box, configure the distance between the stamp box and the position specified with BO_ALIGNMENT_HOR and BO_ALIGNMENT_VER:</p> <pre>[box] BO_DISTANCEX distance BO_DISTANCEY distance</pre> <p>In case of: BO_ALIGNMENT_VER TOP BO_ALIGNMENT_HOR LEFT</p>  |
| 4 | <p>In the section for the stamp box, optionally configure if the reference point is to be oriented to the border of the printable area instead of the border of the document:</p> <pre>[box] BO_ORIGIN VISIBLE_AREA</pre> |

To be continued


Configure the Reference Point of a Stamp Box, Continuation



The reference point is positioned at the top center with a distance to the right of 5 cm and a distance downwards of 3 cm:

Extract of the stamp layout file:

```
...  
BO_ALIGNMENT_HOR    CENTER  
BO_ALIGNMENT_VER    TOP  
BO_DISTANCEX        0.050  
BO_DISTANCEY        0.030  
...
```



Configure an Opaque Stamp

The colors and grayscales of a opaque stamp are displayed, the document contents are covered.

opaque

The text or graphic stamp has been configured:

requirement

→ *Configure a Text Stamp*, page 22

→ *Configure a Graphic Stamp*, page 23

This is how you configure that the stamp is applied opaque:

instructions


| Step | Action |
|------|---|
| 1 | In the section for the stamp box, configure that the stamp is to be applied opaque: [box] BO_CREATION STAMP |

The stamp covers the document contents:



Extract of the stamp layout file:

```
...
BO_CREATION      STAMPS
...
```



Configure a Transparent Colored Stamp

transparent
colored

The colors and grayscales of a transparent colored stamp are displayed, the document contents show through.

requirement

The text or graphic stamp has been configured:

→ *Configure a Text Stamp*, page 22

→ *Configure a Graphic Stamp*, page 23

The PDF_GRAYSTAMP environment variable has been set to color.

instructions

This is how you configure that the stamp is applied transparent colored:


| Step | Action |
|------|---|
| 1 | In the section for the stamp box, configure that the stamp is to be applied transparent colored: [box] BO_CREATION GRAY_STAMP |

example

The stamp is applied as transparent colored stamp onto the document:

Extract of the stamp layout file:

```
...
BO_CREATION      GRAY_STAMP
...
```



Configure a Transparent Gray Stamp

The colors or grayscales of a transparent colored stamp are displayed in grayscales, the document contents show through.

transparent gray

The text or graphic stamp has been configured:

requirement

→ *Configure a Text Stamp*, page 22

→ *Configure a Graphic Stamp*, page 23

This is how you configure that a stamp is applied transparent gray:

instructions

| Step | Action |
|------|---|
| 1 | In the section for the stamp box, configure that the stamp is to be applied transparent gray: <code>[box] BO_CREATION GRAY_STAMP</code> |
| 2 | Set the PDF_GRAYSTAMP environment variable to gray. Alternative with pdfstamp/pdfstamphft: When calling pdfstamp/pdfstamphft, specify the -graystamp parameter with gray. |

The stamp is applied as transparent gray stamp onto the document:


example

Extract of the stamp layout file:

```
...
BO_CREATION      GRAY_STAMP
...
```

environment variable:

`PDF_GRAYSTAMP=gray`



Configure a Gray-Simulated Stamp

gray-simulated

The colors or grayscales of a stamp are simulated by black and white, the document contents show through.

requirement

The text or graphic stamp has been configured:

→ *Configure a Text Stamp*, page 22

→ *Configure a Graphic Stamp*, page 23

instructions

This way, you configure a gray-simulated stamp:

| Step | Action |
|------|---|
| 1 | In the section for the stamp box, configure that the stamp is to be applied gray-simulated: <code>[box] BO_CREATION GRAY_STAMP</code> |
| 2 | Set the PDF_GRAYSTAMP environment variable to simulated. Alternative with pdfstamp/pdfstamphft: When calling pdfstamp/pdfstamphft, specify the -grayscale parameter with simulated. |

 example


The stamp is applied as gray-simulated stamp onto the document:

Extract of the stamp layout file:

```
...
BO_CREATION      GRAY_STAMP
...
...
```

environment variable:

```
PDF_GRAYSTAMP=simulated
```



Configure a Watermark

The watermark is output behind the document, the document contents are not covered.

watermark

The text or graphic stamp has been configured:

requirement

→ *Configure a Text Stamp*, page 22

→ *Configure a Graphic Stamp*, page 23

This is how you configure a watermark:

instructions


| Step | Action |
|------|---|
| 1 | In the section for the stamp box, configure that the stamp is to be applied as watermark behind the document: [box] BO_CREATION WATERMARK |

The stamp will be applied as watermark behind the document.

example

Extract of the stamp layout file:

```
...
BO_CREATION      WATERMARK
...
```



Configure the Stamp Background

background

The stamp background can be displayed in the following variants:

- TRANSPARENT: The document shows through the stamp background. The stamp foreground, that means the stamp text for example, does not show through.
- OPAQUE: The whole stamp including its border covers the document.
- BLANKED: The graphic elements of the stamp have a white border within which the document is covered completely. In the other part of the stamp, the document shows through.

 hint - graphic stamp

With graphic stamps, BLANKED has the same effect as TRANSPARENT.

 Caution - not supported

White areas with the variants OPAQUE and BLANKED are created by overprinting with white color, not by clipping the graphics elements that are to be covered. Therefore, these two variants are not supported by all device types. With pen plotters, for example, only TRANSPARENT is possible as stamp background.

Transparent stamps are supported with restrictions. For example, watermarks can not be used in files generated by gXconvert.

requirement

The text or graphic stamp has been configured:

→ *Configure a Text Stamp*, page 22

→ *Configure a Graphic Stamp*, page 23

instructions


This is how you configure the stamp background:

| Step | Action |
|------|--|
| 1 | In the section for the stamp box, configure how the background of the stamp is to be applied: $[box]$ $BO_BACKGROUND$ <i>background</i> |

To be continued

Configure the Stamp Background, Continuation

The background of the stamp covers the document contents completely, that means it is opaque:



Extract of the stamp layout file:

```
...  
BO_BACKGROUND      OPAQUE  
...
```



Configure an Invisible Stamp

invisible

Invisible stamps are invisible on all backgrounds but can be selected.

background knowledge

In scanned documents which were processed with OCR the found texts cover invisible the document at the original positions. Thereby, these texts can be searched in the document and selected.

requirement

The text or graphic stamp has been configured:

→ *Configure a Text Stamp*, page 22

→ *Configure a Graphic Stamp*, page 23

instructions

This is how you configure an invisible stamp:

| Step | Action |
|------|--|
| 1 | In the used PDF configuration file, check if the font is configured as invisible. <code>PDF.FONT: nr INVISIBLE pdo</code> |
| 2 | In the section for the stamp text, configure that an invisible font is to be used: <code>[text] TX_FONT nr</code> |
| 3 | In the section for the stamp box, configure that no frame is to be drawn: <code>[box] BO_BORDER N</code> |
| 4 | In the section for the stamp box, configure that the background of the stamp is to be transparent. <code>[box] BO_BACKGROUND TRANSPARENT</code> |

 hint -
invisible fonts

The INVISIBLE render mode in the font definition in the PDF configuration file is responsible for the visibility of the font. By changing the render modus, further fonts can be set invisible.

→ *Items of the PDF Configuration File*, page 150

..... To be continued

Configure an Invisible Stamp, Continuation

The stamp is applied onto the document but invisible:



Extract of the PDF configuration file:

```
PDF.font: -4001 Helvetica INVISIBLE helvetica.pdo
```

Extract of the stamp layout file:

```
[Text_0]
...
TX_FONT -4001
...
[Box_0]
...
BO_BORDER N
BO_BACKGROUND TRANSPARENT
...
```

Draw a Frame Around the Stamp Box

frame

The frame is a rectangle around the stamp box which can be than surrounded by a visible frame line for example.

 **Caution -**
graphic stamp
requirement


Frames are only supported for text stamps and not for graphic stamps.

instructions

The reference point of the stamp box has been configured:

→ *Configure the Reference Point of a Stamp Box, page 24*


This is how you draw a frame around a stamp box:

| Step | Action |
|------|--|
| 1 | In the section for the stamp box, configure that a frame is to be drawn around the stamp box: $\begin{array}{ll} [box] & \\ & BO_BORDER \quad Y \end{array}$ |
| 2 | In the section for the stamp box, optionally configure the distance from the stamp box to the frame: $\begin{array}{ll} [box] & \\ & BO_OFFSETX \quad offset \\ & BO_OFFSETY \quad offset \end{array}$  |
| 3 | In the section for the stamp box, optionally configure the color of the frame: $\begin{array}{ll} [box] & \\ & BO_COLOR \quad color \end{array}$ |
| 4 | In the section for the stamp box, optionally configure the line width of the frame: $\begin{array}{ll} [box] & \\ & BO_LWSC \quad linewidth \end{array}$ |

To be continued

Draw a Frame Around the Stamp Box, Continuation

The stamp is applied with a red frame in a distance of 3 mm and a line width of 2 mm:



Extract of the stamp layout file:

[Box_0]

```
...
BO_OFFSETX      0.003
BO_OFFSETY      0.003
BO_BORDER        Y
BO_COLOR         2
BO_LWSC          0.002
...
```



Rotate a Stamp Box

requirement

The reference point of the stamp box has been configured:

→ *Configure the Reference Point of a Stamp Box*, page 24

instructions

This is how you configure that the stamp box is applied rotated:


| Step | Action |
|------|--|
| 1 | In the section for the stamp box, configure the rotation angle for the stamp box: $[box]$ BO_ANGLE <i>angle</i> |

example

The stamp box will be rotated clockwise by 20°:

Extract of the stamp layout file:

```
[Box_0]
...
BO_ANGLE      -20.0
...
```



Configure the Pages to Be Stamped

The text or graphic stamp has been configured:

requirement

→ *Configure a Text Stamp, page 22*


→ *Configure a Graphic Stamp, page 23*

This is how you configure the pages to be stamped:

instructions

| Step | Action |
|------|--|
| 1 | In the section for the stamp box, configure the pages to be stamped: [<i>box</i>] BO_PAGES_TO_STAMP <i>pages</i> |

With PLOSSYS netdome, you can additionally specify if only the first page is to be stamped; if the back sides are to be stamped differently to the front sides and if the page numbers are to be related to the set collation:



→ *Stamp Only the First Page, page 56*

→ *Stamp the Front and Back Sides Differently, page 57*

→ *Relate Pages to Collection Set, page 58*

With pdfstamp/pdfstamphft, you can additionally specify the pages to be stamped:

→ *Specify the Pages to Be Stamped, page 70*

The stamp is applied onto the odd pages:



Extract of the stamp layout file:

```
[Box_0]
BO_PAGES_TO_STAMP    odd
```

The stamp is applied onto each 5th page starting with page 3:

Extract of the stamp layout file:

```
[Box_0]
BO_PAGES_TO_STAMP    3M0D5
```

Preset the Stamp Text

requirement

The text stamp has been configured:

→ *Configure a Text Stamp*, page 22

instructions

This is how you configure a default for a stamp text:

| Step | Action |
|------|--|
| 1 | In the section for the stamp text, configure the text that is to be preset: <pre>[text] TX_TEXT text</pre> |

 example

The Status unknown text is output as text for the stamp unless another stamp text is passed explicitly:

Extract of the stamp layout file:

```
[Text_0]
...
TX_TEXT      "Status unknown"
...
```

Align a Stamp Text to the Stamp Box

Relative to the reference point of the stamp box, you configure the alignment and the starting point of the stamp text.

alignment and starting point

The reference point of the stamp box has been configured:

requirement

→ *Configure the Reference Point of a Stamp Box, page 24*

This is how you position a stamp text relatively to the reference point of the stamp box:

instructions

| Step | Action |
|------|--|
| 1 | <p>In the section for the stamp text, configure the horizontal alignment corresponding to the stamp box:</p> <pre>[text] TX_ALIGNMENT_HOR align CENTER → ÄBg RIGHT → ÄBg LEFT → ÄBg</pre> |
| 2 | <p>In the section for the stamp text, configure the vertical alignment corresponding to the stamp box:</p> <pre>[text] TX_ALIGNMENT_VER align CAP → ÄBg TOP → ÄBg CENTER → ÄBg BASE → ÄBg BOTTOM → ÄBg</pre> |


To be continued

Align a Stamp Text to the Stamp Box, Continuation

instructions,
cont'd

This is how you position a stamp text relatively to the reference point of the stamp box, continuation:

| Step | Action |
|------|---|
| 3 | <p>In the section for the stamp text, configure the vertical and horizontal distance to the reference point of the stamp box:</p> <pre>[text] TX_OFFSETX offset TX_OFFSETY offset</pre> |



The stamp text starts with 1 cm as vertical distance to the reference point of the stamp box and with 2 cm as horizontal distance. The starting point of the stamp text is located on its base line:

Extract of the stamp layout file:

```
[Text_0]
...
TX_ALIGNMENT_HOR      RIGHT
TX_ALIGNMENT_VER      BASE
TX_OFFSETX            0.02
TX_OFFSETY            0.01
...
```

Group Stamp Texts

You can compile multiple stamp texts in a stamp box in order to apply multiline stamps onto the document for example.

The text stamp to be grouped have been configured:

→ *Configure a Text Stamp*, page 22

This is how you group multiple stamp texts to a stamp box:


multiline

requirement

instructions

| Step | Action |
|------|--|
| 1 | In the section for the stamp box, configure the section names of the text stamps to be grouped: [box] BO_CONTENTS text1 text2 ... textn |

The Text1 and Text2 text stamps are applied as two lines in a stamp box:



Extract of the stamp layout file:

```
[STAMP_DEFINITION]
TEXT_DEFINITIONS      Text_1 Text_2
BOX_DEFINITIONS       Box_1
...
[Text_1]
...
TX_ALIGNMENT_HOR     CENTER
TX_ALIGNMENT_VER     TOP
TX_TEXT               "Released"
...
[Text_2]
...
TX_ALIGNMENT_HOR     CENTER
TX_ALIGNMENT_VER     BASE
TX_TEXT               "2013-12-10"
...
[Box_1]
...
BO_CONTENTS          Text_1 Text_2
...
```

PDF-Testpri

Configure the Repetition of a Stamp

repetition

A stamp box can be applied repeatedly in a line or even all over the whole document. For this, a vector or two vectors will be configured. If a vector is specified, the stamp box is repeated along the direction configured by the vector as often as the correspondent document borders are reached. If two vectors are specified, the stamp box is repeated along both directions as often as all document borders are reached.

requirement

The text or graphic stamp has been configured:

→ *Configure a Text Stamp*, page 22

→ *Configure a Graphic Stamp*, page 23

instructions


This is how you configure that the stamp box is repeated:

| Step | Action |
|------|--|
| 1 | If the stamp box is to be repeated in horizontal direction, you configure the vector coordinates for the horizontal direction in the section for the stamp box: $[box]$ $BO_REP_X \quad x \quad y$ |
| 2 | If the stamp box is to be repeated in vertical direction, you configure the vector coordinates for the vertical direction in the section for the stamp box: $[box]$ $BO_REP_Y \quad x \quad y$ |

..... *To be continued*

Configure the Repetition of a Stamp, Continuation


The stamp is repeated over the whole document:



Extract of the stamp layout file:

[Box_0]

```
...
BO_ALIGNMENT_HOR      LEFT
BO_ALIGNMENT_VER      BOTTOM
BO_ANGLE               20.0
BO_DISTANCEX          0.01
BO_DISTANCEY          0.01
BO_FRAME               seal_logo.met
BO REP_X              0.06 0.12
BO REP_Y              0.10 0.05
...
...
```



Configure the Character Width and Spacing

requirement

The text stamp has been configured:

→ *Configure a Text Stamp*, page 22

instructions

This is how you configure the character width and the spacing of the stamp text:

| Step | Action |
|------|--|
| 1 | In the section for the stamp text, configure the factor for the character width: $[\text{text}] \quad \text{TX_EXPANSION} \quad \text{factor}$ |
| 2 | In the section for the stamp text, configure the factor for the additional space between two characters: $[\text{text}] \quad \text{TX_SPACING} \quad \text{factor}$ |

 hint - mirrored


With negative values in TX_EXPANSION and TX_SPACING, the stamp text is applied mirrored.

 example

The stamp text is output with the double character width and the threefold spacing:

Extract of the stamp layout file:

```
[Text_1]
...
TX_EXPANSION      2.0
TX_SPACING        3.0
...
```



4 PLOSSYS netdome - Further Configuration and Operations

This chapter describes what you can configure additionally when stamping with PLOSSYS netdome and how you stamp with PLOSSYS netdome:

| Topic | Page |
|--|------|
| Stamp a Document | 48 |
| Stamp Over All Output Queues | 49 |
| Queue-Specific Stamp | 50 |
| Job-Specific Stamp | 51 |
| Pass a Stamp Text via a Header | 65 |
| Use a Variable in a Stamp Text | 54 |
| Rotate and/or Scale the Stamps with the Document | 55 |
| Stamp Only the First Page | 56 |
| Stamp the Front and Back Sides Differently | 57 |
| Relate Pages to Collection Set | 58 |
| Pass a Graphic File With a Job | 59 |
| Use a Variable in a GKS Metafile | 60 |
| Apply a Flagpage Onto a Document | 61 |

For information about PLOSSYS netdome header, refer to [PLOSSYS_PARAM_TEC].



For information about the PLOSSYS netdome configuration file, plossys.cfg, refer to [NETDOME_TEC].

Stamp a Document

stampings

PLOSSYS netdome stamps a document

- if a general stamp layout file has been configured
→ *Stamp Over All Output Queues*, page 49
 - or if a stamp layout file has been configured for the output queue to which the document is output
→ *Queue-Specific Stamp*, page 50
 - or if a stamp layout file is passed with the output job
→ *Job-Specific Stamp*, page 51
 - and if default stamp texts are available or stamp texts are passed with the output job files.
-

 hint -
no stamps

Stamps will only be applied if stamp boxes are configured in the stamp layout file.

Stamp Over All Output Queues

You can configure stamps for all documents independent of the output queues.


general

This is how you stamp generally over all output queues:

instructions

| Step | Action |
|------|--|
| 1 | Configure the stamps in the stamp layout file %PLSPLT%\general.stp. |
| 2 | Configure the name of the stamp layout file in plossys.cfg in the [SYSTEM] section with the STPFILE item: [SYSTEM] ... STPFILE general.stp ... |
| 3 | Restart PLOSSYS netdome. |

The stamps are identical for all output queues and configured in stamp.cfg:



Extract of plossys.cfg:

```
[SYSTEM]
...
STPFILE      stamp.stp
...
```

Queue-Specific Stamp

queue-specific

You can configure separate stamps for each output queue. The settings are valid for all jobs output to this output queue.

instructions

This is how you stamp specific for an output queue:

| Step | Action |
|------|--|
| 1 | Configure the stamps for the output queue, <i>queue</i> , in the stamp layout file, %PLSPLT%\specific.stp. |
| 2 | Configure the name of the stamp layout file in plossys.cfg in the section for the output queue with the STPFILE item: [queue] ... STPFILE specific.stp ...  hint - default: By default, the stamp layout file with the same name as the output queue and the .stp extension is taken, that means <i>queue.stp</i> for the output queue, <i>queue</i> . |
| 3 | Restart the output queue. |

 **hint - deactivate**

In order to deactivate stamping for an output queue, specify STPFILE "".

 **example**

The stamps are identical for all output queues except printer1 and printer3 and are configured in stamp.cfg: Documents output to printer1 are not stamped. The stamps for the output to printer3 are configured in printer3_stamp.cfg:

Extract of plossys.cfg:

```
[SYSTEM]
...
STPFILE      stamp.stp
...
[printer1]
...
STPFILE      ""
...
[printer3]
...
STPFILE      printer3_stamp.stp
...
```

Job-Specific Stamp

You can configure separate stamps for each output job.

job-specific

For passing a job-specific stamp layout file, it is required that the correspondent gates are configured this way that they save the passed file in the %PLSDATA%\plotserv\associated directory using the correct name. With converters, this behavior is preset.

requirement

Example of the required items for the HPGL gate:

In %PLSROOT%\server\plotserv\gates\hpgl\hpglgate.def:

```
...
[Maingate]
...
stamp = stp
...
[FileExtOptional]
...
stamp = stp
...
...
```




This is how you stamp specific for an output job:

instructions

| Step | Action |
|------|--|
| 1 | Configure the stamps for the output job, <i>jobid</i> , in the stamp layout file, <i>specific.stp</i> . |
| 2 | Pass the stamp layout file together with the other output job files as <i>jobid.stp</i> to the %PLSDATA%\plotserv\associated directory. Alternative: Save the stamp layout file into %PLSPLT% and specify the name of the stamp layout file into the header of the output job as extension at the stamp text: <code>\$ PLS_STAMP_n == "\$specific\$text"</code> |
| 3 | Restart the output queue. |


If the job-specific stamp is a graphic stamp, you have to pass the correspondent graphic file together with the stamp layout file:



→ *Pass a Graphic File With a Job*, page 59

To be continued

Job-Specific Stamp, Continuation



The Excel document, test.xlsx, is stamped according to the stamp layout file, test.stp, the PLS_STAMP_3 stamp is stamped according to the stamp layout file, stamp3.stp:

Extract of the test.hed header:

```
$ PLS_STAMP_3 == "$stamp3.stp$Released"
```

The job files, test.xlsx, test.stp, test.hed and stamp3.stp are passed to PLOSSYS netdome.

Pass a Stamp Text via a Header

The stamp texts can be passed in the header of the output job or specified in the default headers of the gates and so on.

The text stamp has been configured:

→ *Configure a Text Stamp*, page 22

This is how you use texts contained in a header as stamps:

| Step | Action |
|------|---|
| 1 | In the header of the output job, enter the texts line-by-line: \$ PLS_STAMP_n == "text" <i>n</i> can be between 0 and 99. |
| 2 | Pass the header to PLOSSYS netdome together with the other job files. |

In order to deactivate the default for a stamp text in the stamp layout file, enter PLS_STAMP_n == "" with the appropriate number, *n* in the header of the output job. Then, this stamp will not be applied.

If you want to use quotes „ and “ as special characters in a stamp text, you have to quote these by backslashes:

\$ PLS_STAMP_0 == \„My text\“

The stamp texts are passed in the header:

```
...
$ PLS_STAMP_0 == "Released"
$ PLS_STAMP_1 == "2013-12-03"
$ PLS_STAMP_2 == "John Smith"
...
```

header

requirement

instructions

 hint - default

 hint - quotes

 example

Use a Variable in a Stamp Text

variables

With PLOSSYS netdome, you can use PLOSSYS netdome-specific variables, header items or any environment variable in the stamp texts.


PLOSSYS net-dome-specific

This is how you specify a PLOSSYS netdome-specific variable in such a way that its value is output:

`$Variable`

This is how you specify a PLOSSYS netdome-specific variable in such a way that the variable itself is output:

`$$Variable`



The stamp 0 is to be applied with the `$PLS_PLOTTER=device` text:

`$ PLS_STAMP_0 == $$PLS_PLOTTER=$PLS_PLOTTER`

When outputting the document, for example, to the DesignJet output queue, the following is stamped onto the document:

`$PLS_PLOTTER=DesignJet`


environment variable

This is how you specify an environment variable in such a way that its value is output:

`%Variable%`

This is how you specify an environment variable in such a way that the variable itself is output:

`%%Variable%%`



The stamp 2 is to be applied with the `%USERNAME% = user` text:

`$ PLS_STAMP_2 == "%USERNAME%" = %USERNAME%"`

When, for example, the logged-on user, Smith, outputs the document, the following is stamped onto the document:

`%USERNAME% = Smith`

Rotate and/or Scale the Stamps with the Document

The text or graphic stamp has been configured:

requirement

→ *Configure a Text Stamp*, page 22

→ *Configure a Graphic Stamp*, page 23

This is how you configure if the stamp is rotated and/or scaled together with the document:

instructions

| Step | Action |
|------|---|
| 1 | In the stamp layout file in the section for the stamp box, configure if the stamp box is to be rotated with the document: [<i>box</i>] BO_ROTATE ROTATE NOT_ROTATE |
| 2 | In the stamp layout file, configure the default if the stamp box is to be scaled with the document: SCALE_STAMP YES NO |
| 3 | In the stamp layout file in the section for the stamp box, configure if the stamp box is to be scaled with the document: [<i>box</i>] BO_SCALE_BOX YES NO  hint - default: SCALE_STAMP is used as default for BO_SCALE_BOX. |
| 4 | Restart the output queue. |

All stamp except Box_3 are scaled with the document:

example

Extract of the stamp layout file:

```
...
SCALE_STAMP      YES
...
[Box_3]
...
` BO_SCALE_BOX      NO
...
```

Stamp Only the First Page

multi-page

When stamping multi-page documents, you can configure that only the first page is to be stamped.

requirement

The text or graphic stamp has been configured:

→ *Configure a Text Stamp*, page 22

→ *Configure a Graphic Stamp*, page 23

instructions

This is how you configure that only the first page of multi-page documents is stamped:

| Step | Action |
|------|---|
| 1 | In the header of the output job, enter the following: \$ PLS_ONLYFIRSTSTP == YES |
| 2 | Pass the header to PLOSSYS netdome together with the other job files. |

 hint -
further possibili-
ties

In the stamp layout file, you can configure for each stamp box onto which page the stamp is to be applied:

→ *Configure the Pages to Be Stamped*, page 39

 example

In the test.docx document, only the first page is to be stamped:

Extract of the test.hed header:

\$ PLS_ONLYFIRSTSTP == YES

The job files, test.docx and test.hed, are passed to PLOSSYS netdome.

Stamp the Front and Back Sides Differently

When stamping multi-page documents, you can configure that the front and back sides are to be stamped differently.


multi-page

This is how you configure different stamps for the front and the back sides:

instructions

| Step | Action |
|------|--|
| 1 | Configure the stamps of the front sides in the stamp layout file <i>name.stp</i> . |
| 2 | Configure the stamps of the back sides in the extra stamp layout file <i>name.pts</i> . The stamp layout file for the back sides must have the same name as the stamp layout file for the front sides but pts as extension instead of stp. |
| 3 | In the header of the output job, enter the following: \$ PLS_DIFBACKSTP == YES |
| 4 | Restart the output queue. |

In the test.docx document, the front and back sides are to be stamped differently. The stamps for the front sides are configured in stamp.stp:



Extract of the test.hed header:

```
$ PLS_DIFBACKSTP == YES
```

The stamps for the back sides are configured in stamp.pts: The stamp layout files, stamp.stp and stamp.pts are available in PLOSSYS netdome. The job files, test.docx and test.hed, are passed to PLOSSYS netdome.

Relate Pages to Collection Set

requirement

The text or graphic stamp has been configured:

→ *Configure a Text Stamp*, page 22

→ *Configure a Graphic Stamp*, page 23

instructions

This is how you configure that the pages evaluated for stamping relate to the set collation:

| Step | Action |
|------|---|
| 1 | In the stamp layout file in the section for the stamp box, configure that the page numbers for stamping are to be related to the set collation: [box] BO_PAGES_DOMAIN SET |

 example

The stamp is applied onto the odd pages of the set collation:

Extract of the stamp layout file:

```
[Box_0]
BO_PAGES_TO_STAMP    odd
BO_PAGES_DOMAIN      SET
```

Pass a Graphic File With a Job

The graphic stamp has been configured:

requirement

→ *Configure a Graphic Stamp*, page 23

For passing graphic files as graphic stamps, it is required that the correspondent gates are configured this way that they save the passed file in the %PLSDATA%\plotserv\associated directory using the correct name. With converters, this behavior is preset.

Example of the required items for the HPGL gate:

 example -
HPGL gate

In %PLSROOT%\server\plotserv\gates\hpgl\hpglgate.def:

```
...
[Maingate]
...
stampmet = stm
...
[FileExtOptional]
...
stampmet = stm
...
```

This is how you pass a graphic file with the job files:

instructions

| Step | Action |
|------|---|
| 1 | In the stamp layout file in the section for the stamp box, configure that the graphic file is passed with the job: <code>[box]</code> <code>...</code> <code>BO_FRAME *</code> <code>...</code> |
| 2 | Restart the output queue. |
| 3 | Pass the graphic file to PLOSSYS netdome together with the other job files. |

In the test.docx document, the passed graphic file, logo.met, is applied as graphic stamp:

 example

Extract of the stamp layout file:

```
[Box_1]
...
BO_FRAME *
```

The graphic file, logo.met, is passed as test.stm as job file to PLOSSYS netdome.

Use a Variable in a GKS Metafile

variables in GKS metafile

In GKS metafiles, you can specify fix texts and all header items as variable, for example, PLS_PLOTID. The specified header items are replaced by its current values.

requirement

The graphic stamp has been configured:

→ *Configure a Graphic Stamp*, page 23

instructions

This is how you use variables in GKS metafiles:

| Step | Action |
|------|---|
| 1 | In the GKS metafile, specify the GKSM keyword, the text coordinates, the text length and the text or, with \$, the header item. |


example

The GKS metafile, stamp.met, is applied as graphic stamp. In the graphic stamp, the values of some header items are output:

Extract of stamp.met:

```
...
GKSM    13    36    -0.2500    0.35000    12PLS_PLOTOPT:
GKSM    13    36    0.00000    0.35000    12$PLS_PLOTOPT
GKSM    13    37    -0.2500    0.30000    13PLS_PLOTSIZE:
GKSM    13    37    0.00000    0.30000    13$PLS_PLOTSIZE
...

```



Apply a Flagpage Onto a Document

In contrast to the other stamps, the flagpage may be output outside the document as well.

The configuration and the application of a flagpage via PLOSSYS netdome is described in [NETDOME_TEC].



reference

5 pdfstamp/pdfstamphft - Further Configuration and Operations

in this chapter

This chapter describes what you can configure additionally when stamping with pdfstamp/pdfstamphft and how you stamp with pdfstamp/pdfstamphft:

| Topic | Page |
|---|------|
| Stamp a Document | 63 |
| Pass a Stamp Text via a Stamp Text File | 64 |
| Pass a Stamp Text via a Header | 65 |
| Specify a Stamp Text Directly | 66 |
| Use a Variable in a Stamp Text | 67 |
| Change the Displayed Page Number | 69 |
| Specify the Pages to Be Stamped | 70 |
| Keep PDF/A in the Output File | 71 |
| Mark a Stamp | 72 |
| Delete a Stamp | 73 |
| Generate a Stamp As PDF Annotation | 74 |
| Reuse the Temporary Stamp File | 75 |
| Apply a Flagpage Onto a Document | 76 |
| Configure Format-Specific Stamps | 78 |

stamp template

With pdfstamp/pdfstamphft, you can also stamp by using stamp templates.

→ *Stamping Using a Stamp Template*, page 80

Stamp a Document

The stamp layout file containing the configured stamps and the PDF configuration file are available.

requirement


This is how you stamp a document with pdfstamp/pdfstamphft:

instructions

| Step | Action |
|------|---|
| 1 | When calling pdfstamp/pdfstamphft, specify the stamp layout file with the <code>-stp</code> parameter, the PDF configuration file with the <code>-db</code> parameter and optionally further parameters: <code>pdfstamp -f file -stp stpfile -db dbfile ...</code> |

The document, `original.pdf`, is stamped according to the configuration in the stamp layout file, `default.stp`, and the PDF configuration file, `default.db`. The output file is named `stamped.pdf`:

`pdfstamp -f original.pdf -stp default.stp -db default.db
-o stamped.pdf`



Pass a Stamp Text via a Stamp Text File

requirement

The stamp layout file containing the configured stamps and the PDF configuration file are available.

instructions

This is how you use texts contained in a stamp text file as stamps:

| Step | Action |
|------|---|
| 1 | <p>In the stamp text file, <i>stamptextfile</i>, enter the texts line-by-line:</p> <pre>text1 text2 text3 text4 ... </pre> <p>You can configure up to 100 stamps.</p> |
| 2 | <p>When calling pdfstamp/pdfstamphft, specify the stamp text file, <i>stamptextfile</i>, with the <i>-txt</i> parameter:</p> <pre>pdfstamp -f file -stp stpfile -db dbfile -txt stamptextfile</pre> |

example

The document, *original.pdf*, is stamped. The stamp texts are taken from the stamp text file, *stamps.txt*:

```
pdfstamp -f original.pdf -stp default.stp -db default.db
        -txt stamps.txt
```

with the stamp text file, *stamps.txt*:

```
Released
2013-12-03
John Smith
```

Pass a Stamp Text via a Header

The stamp layout file containing the configured stamps and the PDF configuration file are available.

This is how you use texts contained in a header as stamps:


requirement

instructions

| Step | Action |
|------|---|
| 1 | In the header, <i>header</i> , enter the texts line-by-line: <code>\$ PLS_STAMP_n == "textn"</code> <i>n</i> can be between 0 and 99. |
| 2 | When calling pdfstamp/pdfstamphft, specify the <i>header</i> header with the -hed parameter: <code>pdfstamp -f file -stp stpfile -db dbfile -hed header</code> |

If you want to use quotes „ and “ as special characters in a stamp text, you have to quote these by backslashes:

`$ PLS_STAMP_0 == \„My text\“`



The document, original.pdf, is stamped. The stamp texts are taken from the header, stamps.hed:

`pdfstamp -f original.pdf -stp default.stp -db default.db -hed stamps.hed`

with the header, stamps.hed:

```
...
$ PLS_STAMP_0 == "Released"
$ PLS_STAMP_4 == "2013-12-03"
$ PLS_STAMP_5 == "Smith"
...
```

Specify a Stamp Text Directly

requirement

The stamp layout file containing the configured stamps and the PDF configuration file are available.

instructions

This is how you specify texts directly:

| Step | Action |
|------|---|
| 1 | <p>When calling pdfstamp/pdfstamphft, specify the texts with the <code>-tn</code> parameter:</p> <pre>pdfstamp -f file -stp stpfile -db dbfile -tn "text"</pre> |

example

The document, `original.pdf`, is stamped. The Released stamp text is specified directly:

```
pdfstamp -f original.pdf -stp default.stp -db default.db  
-t3 "Released"
```

Use a Variable in a Stamp Text

With pdfstamp/pdfstamphft, you can use the following variables in the stamp texts:

variables


| Variable | Meaning |
|------------|---|
| %PAGE% | Current page number in the document |
| %PAGES% | Total page number of the document |
| %DATE% | <p>the current date in the format specified by the PDF_DATE_FORMAT environment variable.</p> <p>With PDF_DATE_FORMAT, you can combine all format strings provided by the C++ strftime method, for example, %d for day, %B for month name; %H for hour or %M for minute</p>  example - PDF_DATE_FORMAT <p>With set PDF_DATE_FORMAT = %dth of %B %H:%M, the current date and time is output with %DATE% in the format:</p> <p>24th of July 15:26</p> |
| %DATEDE% | <p>Current date in the format: dd.mm.yyyy</p>  example - 24.07.2022 |
| %DATEDEYY% | <p>Current date in the format: dd.mm.yy</p>  example - 24.07.22 |
| %DATEUS% | <p>Current date in the format: mm/dd/yyyy</p>  example - 07.24.2022 |
| %DATEUSYY% | <p>Current date in the format: mm/dd/yy</p>  example - 07/24/22 |

Do not use %PAGE% with PDF documents having many pages! For each page, a temporary PDF file with the stamps is generated. This file increases very quickly and, thereby, stamping takes a long time. If you do not use %PAGE%, the temporary DPF file will be re-used and must be imported only once. This saves space and computing time.




To be continued

Use a Variable in a Stamp Text, Continuation



The document, original.pdf, is stamped. The Released stamp text is output with the current date:

```
pdfstamp -f original.pdf -stp default.stp -db default.db  
-t3 "Released %DATEDE%"
```



Change the Displayed Page Number

The stamp layout file containing the configured stamps and the PDF configuration file are available.

requirement


This is how you change the displayed page number:

instructions

| Step | Action |
|------|---|
| 1 | <p>When calling pdfstamp/pdfstamphft, specify the page number with which the page numbering is to be started with the <code>-startpagecount</code> parameter.</p> <pre>pdfstamp -f file -stp stpfile -db dbfile -startpagecount page</pre>  hint - %PAGE%: <p>%PAGE% is set to the page number specified with <code>-startpagecount</code>.</p> |
| 2 | <p>When calling pdfstamp/pdfstamphft, optionally specify the page number which is to be used as total page count with the <code>-totalpagecount</code> parameter:</p> <pre>-totalpagecount total</pre>  hint - %PAGES%: <p>%PAGES% is set to the total page number specified with <code>-totalpagecount</code>.</p> |

Page numbers are stamped onto to the document, `original.pdf`. The page numbering is generated with the `t0` stamp text and the `%PAGE%` and `%PAGES%` variables. Because this document is to be output as document part, the page numbering is to start at page 17 and 100 is to be displayed as total page number. Then, the page numbering is displayed as "Page 17 of 100", "Page 18 of 100", and so on:

```
pdfstamp -f original.pdf -stp default.stp -db default.db
         -t0 "Page %PAGE% of %PAGES%" -startpagecount 17
         -totalpagecount 100
```



Specify the Pages to Be Stamped

requirement

The stamp layout file containing the configured stamps and the PDF configuration file are available.

instructions

This is how you specify the pages to be stamped:

| Step | Action |
|------|---|
| 1 | When calling pdfstamp/pdfstampHFT, specify the pages to be stamped with the -p parameter: <code>pdfstamp -f file -stp stpfile -db dbfile -p pages</code> |

 example

The document, test.pdf, is stamped. The first three pages are stamped:

`pdfstamp -f test.pdf -stp default.stp -db default.db -p 1-3`

Keep PDF/A in the Output File

The stamp layout file containing the configured stamps and the PDF configuration file are available.

The following requirements must be fulfilled for the keeping of PDF/A:

- The ICC file, srgb.icc, must be available in the %PLSTOOLS%\convcfg directory.
- The SEALRESOURCEPATH environment variable must be set to the %PLSTOOLS%\convcfg directory.
- The input file must be conform to PDF/A.

The conformance level of the output file is set to the conformance level of the input file that means, for example, if the input file is conform to PDF/A-2, the output file will be conform to PDF/A-2, too.

This is how you keep PDF/A for the output file:

conformity level

instructions

| Step | Action |
|------|---|
| 1 | When calling pdfstamp/pdfstamphft, specify with the -forcepdfa parameter that the output file is to be conform to PDF/A and an error message is to be output if this is impossible: <code>pdfstamp -f file -stp stpfile -db dbfile -forcepdfa</code> |

The document, test.pdf, is stamped. The output file, stamped.pdf, is to be conform to PDF/A like the input file:

`pdfstamp -f test.pdf -stp default.stp -db default.db
-o stamped.pdf -forcepdfa`

example

Mark a Stamp

requirement

The stamp layout file containing the configured stamps and the PDF configuration file are available.

instructions

This is how you mark stamps:

| Step | Action |
|------|---|
| 1 | <p>When calling pdfstamp/pdfstamphft, specify the mark for the stamps with the <code>-sti</code> parameter:</p> <pre>pdfstamphft -f file -stp stpfile -db dbfile -sti mark</pre> <p> hint - default mark: When specifying <code>-sti</code> without value, the stamps get the default mark, SEALSTAMP.</p> |

 example

The document, `original.pdf`, is stamped. The stamps get the `to_be_deleted` mark:

```
pdfstamp -f original.pdf -stp default.stp -db default.db  
-sti to_be_deleted
```

Delete a Stamp


The stamps has been marked when stamping: requirement
→ *Mark a Stamp*, page 72

This is how you delete stamps: instructions


| Step | Action |
|------|--|
| 1 | <p>When calling pdfstamp/pdfstamphft, specify the mark for the stamps to be deleted with the -d parameter:</p> <pre>pdfstamphft -f file -d mark</pre> <p> hint - default mark: If you specify -d without value, the stamps with the default mark, SEALSTAMP, are deleted.</p> |

From the document, original.pdf, the stamps marked with to_be_deleted are deleted:

```
pdfstamp -f original.pdf -d to_be_deleted
```



Adobe stamps are deleted with the -da parameter.



Generate a Stamp As PDF Annotation

requirement

The stamp layout file containing the configured stamps and the PDF configuration file are available.

instructions

This is how you generate stamps as PDF annotations:

| Step | Action |
|------|---|
| 1 | When calling pdfstamp/pdfstamphft, specify with the <code>-ma</code> parameter that the stamps are to be generated as PDF annotations: <code>pdfstamp -f file -stp stpfile -db dbfile -ma</code> |
| 2 | When calling pdfstamp/pdfstamphft, optionally specify with the <code>-af</code> parameter with which properties the PDF annotations are to be generated: <code>-af properties</code> |

example

The document, `test.pdf`, is stamped. The stamp is configured in the stamp layout file, `default.stp`, and contains the `Released` text. The stamp is generated as PDF annotation that may be printed but not displayed:

```
pdfstamp -f test.pdf -stp default.stp -db default.db  
-t0 "Released" -ma -af 100100
```

Reuse the Temporary Stamp File

If the sizes of sequential pages in the PDF file are equal or almost equal, the same temporary stamp file is used for stamping. For this page comparison, you can specify a tolerance. Default is 5 mm.

page comparison


This is how you change the tolerance for the page comparison:

instructions

| Step | Action |
|------|--|
| 1 | Set the <code>PLS_PDF_TOLERANCE_IN_MM</code> environment variable to the desired tolerance when comparing the pages. <code>PLS_PDF_TOLERANCE_IN_MM=tolerance</code> |

The document, `original.pdf`, is stamped. The temporary stamp file is to be reused if the sizes of the sequential pages differ by up to 8 mm:

`PLS_PDF_TOLERANCE_IN_MM=8
pdfstamp -f original.pdf`



Apply a Flagpage Onto a Document

flagpage

In contrast to the other stamps, the flagpage may be output outside the document as well.

requirement

The stamp layout file containing the configured stamps and the PDF configuration file are available.

instructions

This is how you configure the layout of the flagpage:

| Step | Action |
|------|---|
| 1 | <p>Generate a flagpage configuration file and configure the position and the layout of the flagpage with the FP_* items within.</p> <p>→ <i>Flagpage Configuration</i>, page 155</p> <p> Caution - not supported: FP_GENERATE, FP_ROTATE and FP_UPVECTOR are not supported by pdfstamp/pdfstamphft.</p> |
| 2 | <p>When calling pdfstamp/pdfstamphft, specify the flagpage configuration file with the -fp parameter and the flagpage texts with the -fptxtn parameters:</p> <pre>pdfstamp -f file -stp stpfile -db dbfile -fp flagpagefile -fptxt1 txt1 ... -fptxtn txtn</pre> |

 example

The document, original.pdf, is stamped. The output file is named flagged.pdf. It contains the flagpage, "John Smith 2013-10-11", according to the configuration in flagpage.cfg:

```
pdfstamp -f original.pdf -stp default.stp -db default.db
-o flagged.pdf -fp flagpage.cfg
-fptxt1 "John Smith 2013-10-11"
```

with the flagpage configuration file, flagpage.cfg


| | |
|--------------|---------|
| FP_POSITION | OUTSIDE |
| FP_SIDE | RIGHT |
| FP_ALIGNMENT | CENTER |
| FP_COLOR | 2 |
| FP_DISTANCEX | 0.001 |
| FP_DISTANCEY | 0.001 |
| FP_FONT | -855 |
| FP_LINEWIDTH | 0.0005 |
| FP_SPACING | 0.000 |
| FP_TEXTSIZE | 0.003 |
| FP_CLEARBG | N |

To be continued

Apply a Flagpage Onto a Document, Continuation

generates flagged.pdf:

 example,
continuation



Configure Format-Specific Stamps

format comparison

The paper size of the document to be stamped is compared to the formats in the SIZE_DESCRIPTION section from top to bottom.

comparison method

For the comparison, you can select between two methods:

- FirstFIT: As soon as the paper size fits completely into a format, the format is selected and the stamp settings having this format prefix are valid.
- FitExact: As soon as the paper size corresponds exactly to one format within a tolerance, the format is selected and the stamp settings having this format prefix are valid.

default

Unless an appropriate format is found, the default stamp settings are taken.

instructions


This is how you configure that the stamp is applied dependent on the format of the document:

| Step | Action |
|------|--|
| 1 | Create the [SIZE_DEFINITIONS] section and configure there the different formats with their widths and lengths in meters: [SIZE_DEFINITIONS] <i>format width length</i> |
| 2 | For the specified formats, create sections containing the stamp settings valid for the <i>format</i> format and configure there the format-specific stamp settings: [<i>format\section</i>] |
| 3 | Create the section without the format prefix and configure there the default stamp settings. |
| 4 | In the FIT_EXACT item without section, optionally configure which comparison method is to be used: NO: The FirstFit method is used. YES: The FitExact method is used. |
| 5 | In the TOLERANCE item without section, optionally configure the tolerance which is to be used when comparing the formats. |

..... To be continued

Configure Format-Specific Stamps, Continuation

Up to DIN A4, the Box_1 stamp is output in black, with all other formats the Box_2 stamp is output in red:



Extract of the stamp layout file:

```
[STAMP_DEFINITION]
    TEXT_DEFINITIONS      Text_2
    BOX_DEFINITIONS       Box_2
    ...
[Text_2]
    ...
    TX_COLOR             3
    ...
[Box_2]
    ...
[SIZE_DEFINITIONS]
    DINA4_P 0.210 0.297
    DINA4_L 0.297 0.210
    ...
[DINA4_P\STAMP_DEFINITION]
    TEXT_DEFINITIONS      Text_1
    BOX_DEFINITIONS       Box_1
    ...
[DINA4_L\STAMP_DEFINITION]
    TEXT_DEFINITIONS      Text_1
    BOX_DEFINITIONS       Box_1
[DINA4_P\Text_1]
    ...
    TX_COLOR             1
    ...
[DINA4_P\Box_1]
    ...
[DINA4_L\Text_1]
    ...
    TX_COLOR             1
    ...
[DINA4_L\Box_1]
    ...
```

6 Stamping Using a Stamp Template

pdfstamp/
pdfstamphft

Stamp templates are supported when stamping via pdfstamp/pdfstamphft.

stamp template

You can use any PDF file as stamp template. As an alternative, you generate a stamp template using pdfstamp/pdfstamphft:

→ *Generate a Stamp Template*, page 81

in this chapter

This chapter deals with the following topics:

| Topic | Page |
|---|------|
| Generate a Stamp Template | 81 |
| Stamp a Document | 82 |
| Position the Stamp Template on the Document | 83 |
| Select Pages From the Stamp Template | 84 |
| Specify the Pages to Be Stamped | 85 |
| Apply the Stamp Template As Watermark | 86 |
| Keep PDF/A in the Output File | 87 |
| Replace a Text in the Stamp Template | 88 |

Generate a Stamp Template

The layout of the stamp boxes and texts is configured in the stamp layout file, *stpfile*: requirement

→ *pdfstamp/pdfstamphft - Further Configuration and Operations*, page 62

This is how you generate a PDF file as stamp template:

instructions

| Step | Action |
|------|---|
| 1 | When calling <i>pdfstamp/pdfstamphft</i> , specify the name under which the stamp template is to be saved with the <i>-o</i> parameter, the stamp layout file with the <i>-stp</i> parameter and the PDF configuration file with the <i>-db</i> parameter: <i>pdfstamp -o template -stp stpfile -db dbfile</i> |
| 2 | When calling <i>pdfstamp/pdfstamphft</i> , optionally specify the width and height of the stamp template in meters with the <i>-x</i> and <i>-y</i> parameters: <i>-x width -y height</i> |
| 3 | When calling <i>pdfstamp/pdfstamphft</i> , specify the stamp texts using one of the available ways: <i>-hed header</i> <i>-tn textn</i> <i>-txt textfile</i> |

The stamp template, *released.pdf*, is generated from the stamp layout file, *default.stp*. The width of the stamp template is 5 cm and its height is 3 cm and the stamp template contains the Released text:

*pdfstamp -o released.pdf -stp default.stp -db default.db
-t0 "Released" -x 0.05 -y 0.03*



example

Stamp a Document

requirement

Any PDF file is available as stamp template or a stamp template has been generated with pdfstamp/pdfstamphft:

→ *Generate a Stamp Template*, page 81

instructions

This is how you stamp a document with a stamp template:

| Step | Action |
|------|---|
| 1 | When calling pdfstamp/pdfstamphft, specify the stamp template with the -stp parameter: <code>pdfstamp -f file -stp template</code> |

example

The document, test.pdf, is stamped with the stamp template, template.pdf:

`pdfstamp -f test.pdf -stp template.pdf`

Position the Stamp Template on the Document

Any PDF file is available as stamp template or a stamp template has been generated with pdfstamp/pdfstamphft:

→ *Generate a Stamp Template*, page 81

This is how you position the stamp template on the document:

requirement

instructions

| Step | Action |
|------|--|
| 1 | When calling pdfstamp/pdfstamphft, specify the horizontal and vertical positions of the stamp template with the -pos parameter: <code>pdfstamp -f file -stp template -pos hv</code> |
| 2 | When calling pdfstamp/pdfstamphft, optionally specify the horizontal and vertical distance to the position with the -off parameter: <code>-off xxy unit</code> |

The document, test.pdf, is stamped with the stamp template, template.pdf. The stamp template is positioned at the bottom right with an horizontal distance of 2 cm and a vertical distance of 3 cm:

`pdfstamp -f test.pdf -stp template.pdf -pos rb -off 2x3 cm`



Select Pages From the Stamp Template

requirement

Any PDF file is available as stamp template or a stamp template has been generated with pdfstamp/pdfstamphft:

→ *Generate a Stamp Template*, page 81

instructions

This is how you specify pages of the stamp template that are to be used as stamps:

| Step | Action |
|------|---|
| 1 | <p>When calling pdfstamp/pdfstamphft, specify the number of the page to be used as stamp with the -pst parameter: <code>pdfstamp -f file -stp template -pst page</code></p> <p>Alternative:</p> <p>Configure the pages in a page configuration file and specify this with the -i parameter when calling pdfstamp/pdfstamphft: <code>pdfstamp -f file -stp template -i pagefile</code></p> |

page configura-
tion file

For each page to be stamped, the page configuration file contains a [Page n] section containing a PLS_STAMP_PAGE=y item with y is the page from the stamp template.

 example -
-pst parameter

The document, test.pdf, is stamped with the stamp template, sealstamp.pdf. The third page of the stamp template contains the stamp with the logo. The pages of the document are to be stamped with the logo:

`pdfstamp -f test.pdf -stp sealstamp.pdf -pst 3`

 example -
page configura-
tion file

The four-page document, m4.pdf, is stamped with the stamp template, sealstamp.pdf. The stamp template contains three stamps for different purposes: cover sheet, trailer sheet and logo. The first page is stamped with the cover sheet stamp, the last one with the trailer sheet stamp and the other pages with the logo. The mapping of the pages is specified in the page configuration file, page.inp:

```
[Page 1]
PLS_STAMP_PAGE=1
[Page 2]
PLS_STAMP_PAGE=3
[Page 3]
PLS_STAMP_PAGE=3
[Page 4]
PLS_STAMP_PAGE=2
```

and the following call:

`pdfstamp -f m4.pdf -stp sealstamp.pdf -i page.inp`

Specify the Pages to Be Stamped

Any PDF file is available as stamp template or a stamp template has been generated with pdfstamp/pdfstamphft:

→ *Generate a Stamp Template*, page 81

This is how you specify the pages to be stamped:

requirement

instructions

| Step | Action |
|------|---|
| 1 | <p>When calling pdfstamp/pdfstamphft, specify the pages to be stamped with the -p parameter:</p> <pre>pdfstamp -f file -stp template -p pages</pre> <p>Alternative:</p> <p>Configure the pages in a page configuration file and specify this with the -i parameter when calling pdfstamp/pdfstamphft:</p> <pre>pdfstamp -f file -stp template -i pagefile</pre> |

For each page to be stamped, the page configuration file contains a [Page *n*] section containing a PLS_STAMP_PAGE=*y* item with *y* is the page from the stamp template.

page configura-
tion file

The document, test.pdf, is stamped with the stamp template, sealstamp.pdf. The odd pages are stamped:

`pdfstamp -f test.pdf -stp sealstamp.pdf -p odd`

example -
-p parameter

The four-page document, m4.pdf, is stamped with the stamp template, sealstamp.pdf. The stamp template contains three stamps for different purposes: cover sheet, trailer sheet and logo. The first page is stamped with the cover sheet stamp, the last one with the trailer sheet stamp and the other pages with the logo. The mapping of the pages is specified in the page configuration file, page.inp:

```
[Page 1]
PLS_STAMP_PAGE=1
[Page 2]
PLS_STAMP_PAGE=3
[Page 3]
PLS_STAMP_PAGE=3
[Page 4]
PLS_STAMP_PAGE=2
```

example -
page configura-
tion file

and the following call:

`pdfstamp -f m4.pdf -stp sealstamp.pdf -i page.inp`

Apply the Stamp Template As Watermark

requirement

Any PDF file is available as stamp template or a stamp template has been generated with pdfstamp/pdfstampHFT:

→ *Generate a Stamp Template*, page 81

instructions

This is how you apply a stamp template as watermark onto the document:

| Step | Action |
|------|--|
| 1 | When calling pdfstamp/pdfstampHFT, specify with the <code>-usepdfaswatermark</code> parameter that the stamp template is to be stamped as watermark: <code>pdfstamp -f file -stp template -usepdfaswatermark</code> |

example

The document, test.pdf, is stamped with the stamp template, template.pdf. The stamps of the stamp template are applied as watermarks onto the document.

`pdfstamp -f test.pdf -stp template.pdf -usepdfaswatermark`

Keep PDF/A in the Output File

Any PDF file is available as stamp template or a stamp template has been generated with pdfstamp/pdfstamphft: requirement

→ *Generate a Stamp Template*, page 81

The following requirements must be fulfilled for the keeping of PDF/A:

- The ICC file, srgb.icc, must be available in the %PLSTOOLS%\convcfg directory.
- The SEALRESOURCEPATH environment variable must be set to the %PLSTOOLS%\convcfg directory.
- The input file and the stamp template must be conform to PDF/A.

The conformity level of the output file is set to the highest conformity level of the input files this means, for example, that if at least one of the input files is conform to PDF/A-2, the output file will be conform to PDF/A-2, too. The smallest sub level among the input files is taken as sub level of the output file. The comparison order is b, u and a.

conformance level

This is how you keep PDF/A for the output file:

instructions

| Step | Action |
|------|---|
| 1 | When calling pdfstamp/pdfstamphft, specify with the -forcepdfa parameter that the output file is to be conform to PDF/A and an error message is to be output if this is impossible: <code>pdfstamp -f file -stp template -forcepdfa</code> |

The document, test.pdf, is stamped with the stamp template, template.pdf. The output file, stamped.pdf, is to be conform to PDF/A like the input file:

`pdfstamp -f test.pdf -stp template.pdf -o stamped.pdf
-forcepdfa`

example

Replace a Text in the Stamp Template

stamp template

When stamping a document with a stamp template, you can replace the texts contained in the stamp template.

 **Caution** - restriction

Please note the following restrictions when replacing texts in a stamp template:

- The text to be replaced can not be found if, for example, the stamp text does not exist as text but as an amount of vectors.
- Some characters in the replacing text may not be displayed unless the font has been embedded in the stamp text completely.
- The border may no longer fit after the replacement due the border will not be adjusted to the new text.

instructions


This is how you replace a text in the stamp template:

| Step | Action |
|------|---|
| 1 | <p>When calling pdfstamp/pdfstamphft, specify the text to be replaced with the -k parameter and the new text with the -t parameter:</p> <pre>pdfstamp.exe -f file -stp template -k oldtext -t newtext</pre> |

 example

The document, test.pdf, is stamped with the stamp template, template.pdf. In the stamp template, the USER text is replaced by John Smith:

```
pdfstamp -f test.pdf -stp template.pdf -k USER -t "John Smith"
```



Reference

7 Parameter of pdfstamp/pdfstampht - Reference

The programs have the following mandatory parameters:

| Mandatory Parameter | Page |
|---|------|
| -stp <string> Stamp Layout File or Stamp Template | 120 |

mandatory parameter

The programs have the following optional parameters:

| Optional Parameter | Page |
|--|------|
| -af <binary> Properties of the PDF Annotation | 94 |
| -d <string> Delete a Stamp | 95 |
| -da <string> Delete an Adobe Stamp | 96 |
| -db <string> PDF Configuration File | 97 |
| -f <string> Input File | 98 |
| -forcepdfa Keep PDF/A in the Output File | 99 |
| -fp <string> Flagpage Configuration File | 100 |
| -fptxt<n> <string> Flagpage Texts | 101 |
| -graystamp <enumeration> Display of the Gray Stamps | 102 |
| -h Output the Usage | 103 |
| -hed <string> Header with Stamp Texts | 104 |
| -i <string> Page Configuration File | 105 |
| -k <string> Text to Be Replaced in the Stamp Template | 106 |
| -keep Do Not Delete Temporary Stamp Files | 107 |
| -ma Generate the Stamp As a PDF Annotation | 108 |
| -nopdfa Do No Force PDF/A | 109 |
| -o <string> Output File | 110 |
| -off <string> Offset of the Stamp Template | 111 |
| -p <enumeration> Pages to Be Stamped | 112 |
| -pos <string> Position of the Stamp Template | 113 |
| -pst <enumeration> Page From the Stamp Template | 114 |
| -rec Stamp Embedded Files Recursively | 115 |
| -setimagemask Change the White Background to Transparent | 116 |

optional parameters

..... *To be continued*

Parameter of pdfstamp/pdfstamphft - Reference,

Continuation

The programs have the following optional parameters, continuation:

optional parameters, contd.

| Optional Parameter | Page |
|---|------|
| -setuu <float> UserUnit | 117 |
| -startpagecount <integer> Start of the Page Numbering | 118 |
| -sti <string> Mark a Stamp | 119 |
| -t <string> New Text for the Stamp Template | 121 |
| -t<n> <string> Stamp Text | 122 |
| -totalpagecount <integer> Total Page Number | 123 |
| -txt <string> Stamp Text File | 124 |
| -uselogicalpage Consider startpagecount | 125 |
| -usepdfaswatermark Stamp As Watermark | 126 |
| -x <float> Width of the Stamp Template | 127 |
| -y <float> Height of the Stamp Template | 128 |

-af <binary> Properties of the PDF Annotation

purpose With the -af (annotation flag) parameter, you specify the properties of the PDF annotations when generating stamps as PDF annotations using the -ma parameter.

type This parameter is optional.

value With -af, you specify the following value:

| Value | Description |
|-------------|---|
| <i>flag</i> | <p>Properties of the PDF annotations as array of bits:</p> <p>Starting from the right, the bits have the following meanings:</p> <ul style="list-style-type: none"> Bit 1: Invisible Bit 2: Hidden Bit 3: Print Bit 4: NoZoom Bit 5: NoRotate Bit 6: NoView Bit 7: Readonly Bit 8: Locked Bit 9: ToggleNoView Bit 10: LockedContents <p> reference - annotation flag:</p> <p>For further information about the single bits in the annotation flag, refer to [PDF_REF].</p> |

default Default is 100, that means the print bit is set, the other bits are not set.



example The document, original.pdf, is stamped with the texts contained in default.txt. The stamps are generated as PDF annotations that may be printed but not displayed:

```
pdfstamp -f original.pdf -stp default.stp -db default.db
-txt default.txt -ma -af 100100
```

related parameters There is a close connection to the following parameters:

| Related Parameter | Page |
|--|------|
| -ma Generate the Stamp As a PDF Annotation | 108 |

-d <string> Delete a Stamp

With the -d (delete) parameter, you specify that the stamps with the specified or the default mark, SEALSTAMP, are to be deleted. The mark is set with the -sti parameter.

purpose

This parameter is optional.

type

With -d, you can specify the following value:

value

| Value | Description |
|-------------|----------------------------------|
| <i>name</i> | Mark of the stamps to be deleted |

If you specify -d without value, the stamps with the default mark, SEALSTAMP, are deleted.

default

From the document, original.pdf, the stamp marked with stamp1 is deleted:

```
pdfstamp -f original.pdf -stp default.stp -db default.db
-d stamp1
```

examples

From the input file, original.pdf, all stamps marked with the default mark, SEALSTAMP, are deleted:

```
pdfstamp -f original.pdf -stp default.stp -db default.db -d
```

There is a close connection to the following parameters:

related parameters

| Related Parameter | Page |
|----------------------------|------|
| -d <string> Delete a Stamp | 95 |
| -sti <string> Mark a Stamp | 119 |

-da <string> Delete an Adobe Stamp

purpose With the -da (delete adobe stamp) parameter, you specify that the Adobe stamps with the specified name are to be deleted. Examples of Adobe stamps are header and footer from Adobe LiveCycle.

type This parameter is optional.

value With -da, you can specify the following value:

| Value | Description |
|-------------|--|
| <i>name</i> | Name of the Adobe stamps to be deleted |

default If you do not specify -da or specify it without value, the Adobe stamps will not be deleted.



hint --d The -da and -d parameters may be specified both in one call.



examples From the document, original.pdf, the Adobe stamp Header is deleted:

```
pdfstamp -f original.pdf -stp default.stp -db default.db  
-da Header
```

related parameters

There is a close connection to the following parameters:

| Related Parameter | Page |
|----------------------------|------|
| -d <string> Delete a Stamp | 95 |

-db <string> PDF Configuration File

With the -db parameter, you specify the text file in which the DPF generation is configured.

The parameter is mandatory unless using a stamp template.

With -db, you specify the following value:

| Value | Description |
|-------------|---|
| <i>file</i> | Name of the file containing the configuration of the PDF generation |

There is no default.

→ *PDF Configuration File (.db)*, page 149

The PDF configuration file is a system file that must be modified in very rare case only.

The document, `original.pdf`, is stamped according to the stamp layout file, `default.stp`, and with the texts contained in `default.txt`. The PDF generation is configured in the PDF configuration file, `output.db`:

```
pdfstamp -f original.pdf -stp default.stp -db output.db
          -txt default.txt
```

purpose

type

value

default

file syntax

 hint - system file

 example

-f <string> Input File

| purpose | With the -f parameter, you specify the document to be stamped. | | | | |
|-------------|--|-------|-------------|-------------|------------------------|
| type | The parameter is mandatory when using pdfstamp/pdfstamphft for stamping a document. The parameter must not be specified when using pdfstamp/pdfstamphft for generating a stamp template. | | | | |
| value | With -f, you specify the following value: | | | | |
| | <table border="1"><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td><i>file</i></td><td>Name of the input file</td></tr></tbody></table> | Value | Description | <i>file</i> | Name of the input file |
| Value | Description | | | | |
| <i>file</i> | Name of the input file | | | | |
| default | If you do not specify the -f parameter but the -o parameter, a stamp template is generated. | | | | |
| example | The document, original.pdf, is stamped according to the stamp layout file, default.stp, and with the texts contained in default.txt. <pre>pdfstamp -f original.pdf -stp default.stp -db default.db -txt default.txt</pre> | | | | |

-forcepdfa Keep PDF/A in the Output File

With the -forcepdfa parameter, you specify that the output file is to be conform to PDF/A.

The following requirements must be fulfilled for creating PDF/A:

- The ICC file, srgb.icc, must be available in the %PLSTOOLS%\convcfg directory.
- The SEALRESOURCEPATH environment variable must be set to the %PLSTOOLS%\convcfg directory.
- All input files, that means the stamp template as well, must be conform to PDF/A.



This parameter is optional.

type

By default, the operations that make sense for PDF/A are executed, such as embedding the fonts for the stamp, but the output file does not have to be conform to PDF/A.

default

The document, original.pdf, is stamped with the stamp template, template.pdf. The stamped file is to be conform to PDF/A:

```
pdfstamp -f original.pdf -stp template.pdf -forcepdfa
```



There is a close connection to the following parameters:

related parameters

| Related Parameter | Page |
|----------------------------|------|
| -nopdfa Do Not Force PDF/A | 109 |

-fp <string> Flagpage Configuration File

purpose With the -fp (flagpage) parameter, you specify a text file in which the layout of the flagpage is configured.

type This parameter is optional.

value With -fp, you specify the following value:

| Value | Description |
|-------------|--|
| <i>file</i> | Name of the text file containing the configuration of the flagpage |

default There is no default.

file syntax → *Flagpage Configuration*, page 155

 **example** The flagpage with the date and the time is applied onto the document, original.pdf. The layout of the flagpage is configured in flagpage.fp:

```
pdfstamp -f original.pdf -db default.db -fp flagpage.fp
-fptxt1 "2013-09-12" -fptxt2 "15:46"
```

related parameters There is a close connection to the following parameters:

| Related Parameter | Page |
|-----------------------------------|------|
| -fptxt<n> <string> Flagpage Texts | 109 |

-fptxt<n> <string> Flagpage Texts

With the `-fptxt n` (flagpage text) parameter, you specify the texts for the flagpage.

purpose

The parameter is mandatory when specifying the `-fp` parameter.

type

With `-fptxt n` , you specify the following value:

value

| Value | Description |
|--------|---|
| $text$ | Text of the flagpage n with n from 1 to 5 |

There is no default.

default

The flagpage with the date and the time is applied onto the document, `original.pdf`. The layout of the flagpage is configured in `flagpage.fp`:

```
pdfstamp -f original.pdf -db default.db -fp flagpage.fp
-fptxt1 "2013-09-12" -fptxt2 "15:46"
```



example

There is a close connection to the following parameters:

related parameters

| Related Parameter | Page |
|---|------|
| <code>-fp <string></code> Flagpage Configuration File | 109 |

-graystamp <enumeration> Display of the Gray Stamps

purpose With the -graystamp parameter, you specify how the gray stamps are to be displayed.

gray stamp For a gray stamp, the BO_CREATION item in the stamp layout file is set to GRAY_STAMP.

→ *Stamp Layout File (.stp)*, page 130


type This parameter is optional.

value With -graystamp, you can specify the following values:

| Value | Description |
|-----------|--|
| color | The gray stamps are displayed transparent colored. |
| gray | The gray stamps are displayed transparent gray. |
| simulated | The gray stamps are simulated by Black and White. |

default Default is gray, that means that gray stamps are displayed transparent gray.

alternative As an alternative to the specification of the -graystamp parameter, you can set the PDF_GRAYSTAMP environment variable to the desired value.



The document, original.pdf, is stamped with a transparent color stamp.

```
pdfstamp -f original.pdf -stp default.stp -db default.db
          -txt default.txt -graystamp color
```

-h Output the Usage

With the -h parameter, you get the usage.


purpose

This parameter is optional.

type

All parameters will be displayed:

`pdfstamp -h`



-hed <string> Header with Stamp Texts

purpose With the -hed Parameter, you specify a header containing the stamp texts.

type For a text stamp, the stamp text must be specified using one of the available ways (-hed, -txt, -tn, TX_TEXT), otherwise the stamp will not be applied.




The texts specified with -tn take priority to the texts that are passed in the header with stamp texts and in the stamp text file.

value With -hed, you specify the following value:

| Value | Description |
|-------------|---|
| <i>file</i> | Name of the header containing the stamp texts |

default There is no default.

file syntax The syntax of the header is described in [PLOSSYS_PARAM_TEC].



The document, original.pdf, is stamped. The stamp texts are passed in the default.hed header:

```
pdfstamp -f original.pdf -stp default.stp -db default.db
-hed default.hed
```

with the default.hed header:

```
...
$ PLS_STAMP_0 == "Released"
$ PLS_STAMP_1 == "2013-12-03"
$ PLS_STAMP_2 == "John Smith"
...
```

related parameters There is a close connection to the following parameters:

| Related Parameter | Page |
|-------------------------------|------|
| -txt <string> Stamp Text File | 124 |
| -t<n> <string> Stamp Text | 122 |

-i <string> Page Configuration File

With the `-i` parameter, you specify a text file with the configuration which pages from the stamp template are to be stamped on which pages of the output file.

purpose

This parameter is optional.

type

With `-i`, you specify the following value:

value

| Value | Description |
|-------------------|--|
| <code>file</code> | Name of the text file containing the page settings |

By default, all pages are stamped.

default

For each page to be stamped, the page configuration file contains a [Page *n*] section containing a `PLS_STAMP_PAGE=y` item with *y* is the page from the stamp template.

file syntax

The four-page document, `original.pdf`, is stamped with different pages from the three-page stamp template, `template.pdf`. The mapping is configured in `layout.ini`:

 example

```
pdfstamp -f original.pdf -stp template.pdf -i layout.ini
```

with the page configuration file, `layout.ini`:

```
[Page 1]
PLS_STAMP_PAGE=1
[Page 2]
PLS_STAMP_PAGE=3
[Page 3]
[Page 4]
PLS_STAMP_PAGE=2
```

results in:

- Page 1 of `original.pdf` is stamped with page 1 from `template.pdf`.
- Page 2 of `original.pdf` is stamped with page 3 from `template.pdf`.
- Page 3 of `original.pdf` is not stamped.
- Page 4 of `original.pdf` is stamped with page 2 from `template.pdf`.

-k <string> Text to Be Replaced in the Stamp Template

purpose With the -k (keyword) parameter, you specify the text to be replaced in the stamp template.

type This parameter is optional.

value With -k, you specify the following value:

| Value | Description |
|------------|---|
| <i>key</i> | Text to be replaced in the stamp template by another text; texts with blanks must be quoted with ". |

default There is no default.

 **example** The document, original.pdf, is stamped with the stamp template, template.pdf. The USER text is replaced by John Smith:

```
pdfstamp -f original.pdf -stp template.pdf
-k USER -t "John Smith"
```

related parameters There is a close connection to the following parameters:

| Related Parameter | Page |
|---|------|
| -t <string> New Text for the Stamp Template | 121 |

-keep Do Not Delete Temporary Stamp Files

With the -keep parameter, you specify that the temporary stamp file are not to be deleted.

This parameter is optional.

By default, the temporary stamp files are deleted.

The document, original.pdf, is stamped with the stamp template, template.pdf. The temporary stamp files are kept.

```
pdfstamp -f original.pdf -stp template.pdf -keep
```



default

purpose


type

-ma Generate the Stamp As a PDF Annotation

purpose With the -ma (make annotation) parameter, you specify that the stamps are generated as PDF annotations.

type This parameter is optional.

default By default, the stamps are generated as graphic elements.



example The document, original.pdf, is stamped with the texts contained in default.txt. The stamps are generated as PDF annotations:

```
pdfstamp -f original.pdf -stp default.stp -db default.db  
-txt default.txt -ma
```

related parameters There is a close connection to the following parameters:

| Related Parameter | Page |
|---|------|
| -af <binary> Properties of the PDF Annotation | 94 |

-nopdfa Do Not Force PDF/A

With the `-nopdfa` parameter, you specify that the operations that make sense for PDF/A are not to be executed. Such an operation is, for example, embedding the fonts for the stamps.

purpose

This parameter is optional.

type

By default, the operations that make sense for PDF/A are executed.

default

The document, `original.pdf`, is stamped with the stamp template, `template.pdf`. The operations that make sense for PDF/A will not be executed:
`pdfstamp -f original.pdf -stp template.pdf -nopdfa`



example

There is a close connection to the following parameters:

related parameters

| Related Parameter | Page |
|---|------|
| <code>-forcepdfa</code> Keep PDF/A in the Output File | 99 |

-o <string> Output File

| purpose | With the -o (output) parameter, you specify the output file. | | | | |
|---|---|-------|-------------|-------------|-------------------------|
| type | The parameter is optional when using pdfstamp/pdfstamphft for stamping a document. The parameter is mandatory when using pdfstamp/pdfstamphft for generating a stamp template. | | | | |
| value | With -o, you specify the following value: | | | | |
| | <table border="1"><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td><i>file</i></td><td>Name of the output file</td></tr></tbody></table> | Value | Description | <i>file</i> | Name of the output file |
| Value | Description | | | | |
| <i>file</i> | Name of the output file | | | | |
| default | By default, the output file overwrites the input file when stamping a document. | | | | |
|  example - stamp file | The document, original.pdf, is stamped. The stamped output file, stamped.pdf, is generated: <pre>pdfstamp -f original.pdf -o stamped.pdf -stp default.stp -db default.db -txt default.txt</pre> | | | | |
|  example - generate stamp template | The stamp template, template.pdf, is generated with the stamp layout file, default.stp, the PDF configuration file, default.db, and the stamp texts in default.txt: <pre>pdfstamp -o template.pdf -stp default.stp -db default.db -txt default.txt</pre> | | | | |

-off <string> Offset of the Stamp Template

With the -off (offset) parameter, you specify the horizontal and vertical distance of the position of the stamp template specified with the -pos parameter.

purpose

This parameter is optional.

type

With -off, you specify the following value:

value

| Value | Description |
|------------------------|--|
| <code>xx y unit</code> | <p>Horizontal and vertical distance of the stamp template to the specified position in direction of the document center.</p> <p>Available values for x and y: floats</p> <p>Available values for <i>unit</i>:</p> <ul style="list-style-type: none"> mm: Millimeter (Default) cm: centimeter m: Meter |

Default is `0.0x0.0`, that means that the stamp template have no distance to the specified position.

default

The document, `original.pdf`, is stamped with the stamp template, `template.pdf`. The stamp is positioned at the top right with an horizontal distance of 2 cm and a vertical distance of 1,5 cm:

```
pdfstamp -f original.pdf -stp template.pdf -pos rt
-off 2.0x1.5 cm
```



example

There is a close connection to the following parameters:

related parameters

| Related Parameter | Page |
|--|------|
| -pos <string> Position of the Stamp Template | 113 |

-p <enumeration> Pages to Be Stamped


purpose With the -p (pages) parameter, you specify the pages to be stamped.

type This parameter is optional.

values With -p, you can specify the following values:

| Value | Description |
|--------------|---|
| <i>0</i> | All pages will be stamped. |
| <i>page</i> | The <i>page</i> page will be stamped. |
| <i>i,j,k</i> | The pages <i>i</i> , <i>j</i> , and <i>k</i> will be stamped. |
| <i>i..j</i> | The pages in the range from <i>i</i> to <i>j</i> will be stamped. |
| <i>even</i> | All even pages will be stamped. |
| <i>last</i> | Only the last page will be stamped. |
| <i>odd</i> | All odd pages will be stamped. |

default Default is *0*, that means all pages are stamped.



example In the document, `original.pdf`, the third page is stamped:

```
pdfstamp -f original.pdf -stp default.stp -db default.db
          -txt default.txt -p 3
```

-pos <string> Position of the Stamp Template

With the -pos (position) parameter, you specify the position where the stamp template is to be applied onto the document.

This parameter is optional.

With -pos, you specify the following value:

| Value | Description |
|-----------|---|
| <i>hv</i> | <p>Position of the stamp template on the document</p> <p>Available values for <i>h</i>:</p> <ul style="list-style-type: none"> l: left m: middle r: right <p>Available values for <i>v</i>:</p> <ul style="list-style-type: none"> b: bottom m: middle t: top |

Default is *lb*, that means at the bottom left.

The document, *original.pdf*, is stamped with the stamp template, *template.pdf*. The stamp is displayed in the center:

```
pdfstamp -f original.pdf -stp template.pdf -pos mm
```

There is a close connection to the following parameters:

| Related Parameter | Page |
|--|------|
| -off <string> Offset of the Stamp Template | 111 |

-pst <enumeration> Page From the Stamp Template

.....
purpose With the -pst (page stamp template) parameter, you specify which page of a multi-page stamp template are to be used as stamp.

.....
type This parameter is optional.

.....
values With -pst, you specify the following value:

| Value | Description |
|-------------|---|
| <i>page</i> | The <i>page</i> page from the stamp template will be used as stamp. |

.....
default Default is 1, that means that the first page of the stamp template is used.

 example The document, original.pdf, is stamped with third page of the stamp template, template.pdf.
`pdfstamp -f original.pdf -stp template.pdf -pst 3`

-rec Stamp Embedded Files Recursively

With the -rec (recursive) parameter, you specify that the PDF files embedded in PDF collections are to be stamped recursively.

purpose

The -rec parameter is only available for pdfstamphft.

 **Caution** -
pdfstamphft

This parameter is optional.

type

By default, the embedded PDF files are not stamped.

default

The document, collection.pdf, is stamped with the stamp template, template.pdf. All embedded PDF files are stamped recursively:

`pdfstamphft -f collection.pdf -stp template.pdf -rec`

 example

-setimagemask Change the White Background to Transparent

purpose

With the `-setimagemask` parameter, you specify that a white background is set transparent. For this, the ImageMask is set to transparent.

 hint - watermark

The `-setimagemask` parameter is important with watermarks for example due to the actual transparent but white displayed background would cover the watermark.

type

This parameter is optional.

default

By default, the background displayed in white remains white.

 example

The document, `original.pdf`, is stamped as watermark with the stamp template, `template.pdf`. The white background is set to transparent:

```
pdfstamp -f original.pdf -stp template.pdf -usepdfaswatermark  
-setimagemask
```

-setuu <float> UserUnit

With the -setuu (set user unit) parameter, you specify the UserUnit to be set in the output file.

purpose

Adobe Acrobat Reader can only display PDF files up to a size of 14400 units (200 inch). If a UserUnit is set in the PDF file, all internal metric coordinates are divided by the value of the UserUnit. Because Adobe Acrobat Reader and other viewers evaluate the UserUnit, the correct size is identified further on.

background knowledge

This parameter is optional.

type

With -setuu, you specify the following value:

value

| Value | Description |
|-----------------|---|
| <i>userunit</i> | UserUnit; if the value is smaller than 1.0, the UserUnit will be evaluated automatically if required. |

By default, the UserUnit will not be set.

default

As an alternative to the specification of the -setuu parameter, you can set the PDF_SET_USER_UNIT environment variable.

alternative


You can display the UserUnit of a PDF file by calling pdfprae:



→ [PDFTOOLS_TEC]

The document, original.pdf, is stamped with the stamp template, template.pdf. The UserUnit is set to 2:

```
pdfstamp -f original.pdf -stp template.pdf -setuu 2.0
```



-startpagecount <integer> Start of the Page Numbering

purpose With the -startpagecount parameter, you specify a number with which the page numbering in the %PAGE% variable is to be started.

type This parameter is optional.

value With -startpagecount, you specify the following value:

| Value | Description |
|-------------|---|
| <i>page</i> | Page with which the page numbering in %PAGE% starts |

default Default is 1, that means that the page numbering starts with 1.

example

Page numbers are stamped onto to the 34-page document, original.pdf. The page numbering is generated with the t0 stamp text and the %PAGE% and %PAGES% variables. Because this document is to be output as document part, the page numbering is to start at page 17. Then, the page numbering is displayed as "Page 17 of 50", "Page 18 of 50", and so on:

```
pdfstamp -f original.pdf -stp default.stp -db default.db
-t0 "Page %PAGE% of %PAGES%" -startpagecount 17
```

related parameters There is a close connection to the following parameters:

| Related Parameter | Page |
|---|------|
| -totalpagecount <integer> Total Page Number | 123 |

-sti <string> Mark a Stamp

With the -sti (sticky) parameter, you specify that the stamps get a mark. By means of this mark, you can delete the stamps with the -d parameter later on.

purpose

This parameter is optional.

type

With -sti, you specify the following value:

value

| Value | Description |
|-------------|-------------------------------|
| <i>name</i> | Text set as mark at the stamp |

Unless you specify -sti, the stamps will not be marked. When specifying -sti without value, the stamps get the default mark, SEALSTAMP.

default

The document, original.pdf, is stamped. The stamps get the stamp1 mark:

```
pdfstamp -f original.pdf -stp default.stp -db default.db  
-sti stamp1
```



examples

The document, original.pdf, is stamped. The stamps get the default mark, SEALSTAMP:

```
pdfstamp -f original.pdf -stp default.stp -db default.db -sti
```

There is a close connection to the following parameters:

related parameters

| Related Parameter | Page |
|----------------------------|------|
| -d <string> Delete a Stamp | 95 |

-stp <string> Stamp Layout File or Stamp Template

purpose With the -stp parameter, you specify a text file in which the layout of the stamps is configured or the stamp template.

type The parameter is mandatory.

value With -stp, you specify the following value:

| Value | Description |
|-------------|--|
| <i>file</i> | Name of the text file containing the stamp configuration or name of the stamp template |

default There is no default.

file syntax → *Stamp Layout File (.stp)*, page 130

 example The document, original.pdf, is stamped. The layout of the stamps is configured in the stamp layout file, stamp.stp:

```
pdfstamp -f original.pdf -stp stamp.stp -db default.db  
-txt default.txt
```

-t <string> New Text for the Stamp Template

With the -t (text) parameter, you specify the text in the stamp template that is to replace the text specified with the -k parameter.

The parameter is mandatory when specifying the -k parameter.

With -t, you specify the following value:

| Value | Description |
|-------------|---|
| <i>text</i> | Text to be replaced in the stamp template by another text; texts with blanks must be quoted with ". |

There is no default.

The document, original.pdf, is stamped with the stamp template, template.pdf. The USER text is replaced by John Smith:

```
pdfstamp -f original.pdf -stp template.pdf
-k USER -t "John Smith"
```

There is a close connection to the following parameters:

| Related Parameter | Page |
|---|------|
| -k <string> Text to Be Replaced in the Stamp Template | 106 |

-t<n> <string> Stamp Text

purpose

With the `-tn` parameters, you specify the stamp texts.

type

For a text stamp, the stamp text must be specified using one of the available ways (`-hed`, `-txt`, `-tn`, `TX_TEXT`), otherwise the stamp will not be applied.

 hint - priority

The texts specified with `-tn` take priority to the texts that are passed in the header with stamp texts and in the stamp text file.

value

With `-tn` you specify the following value:

| Value | Description |
|-------------------|---|
| <code>text</code> | Text of the stamp <i>n</i> with <i>n</i> from 0 to 99 |

default

There is no default.

 example

The document, `original.pdf`, is stamped. The stamp texts are passed with the `-t0`, `-t9` and `-t10` parameters:

```
pdfstamp -f original.pdf -stp default.stp -db default.db
-t0 "Released" -t9 "25.5.2013" -t10 "John Smith"
```

related parameters

There is a close connection to the following parameters:

| Related Parameter | Page |
|--|------|
| <code>-hed <string></code> Header with Stamp Texts | 104 |
| <code>-txt <string></code> Stamp Text File | 124 |

-totalpagecount <integer> Total Page Number

With the -totalpagecount parameter, you specify the total page number. The %PAGES% variable will be set to this value.

This parameter is optional.

With -totalpagecount, you specify the following value:

| Value | Description |
|------------------|---|
| <i>totalpage</i> | Total page number of the document (%PAGES%) |

Default is the actual page number of the document.

Page numbers are stamped onto the document, original.pdf. The page numbering is generated with the *t0* stamp text and the %PAGE% and %PAGES% variables. Because this document is to be output as document part, the page numbering is to start at page 17 and 100 is to be displayed as total page number. Then, the page numbering is displayed as "Page 17 of 100", "Page 18 of 100", and so on:

```
pdfstamp -f original.pdf -stp default.stp -db default.db
-t0 "Page %PAGE% of %PAGES%" -startpagecount 17
-totalpagecount 100
```

There is a close connection to the following parameters:

| Related Parameter | Page |
|---|------|
| -startpagecount <integer> Start of the Page Numbering | 118 |

-txt <string> Stamp Text File

purpose With the -txt parameter, you specify a text file containing the stamp texts.

type For a text stamp, the stamp text must be specified using one of the available ways (-hed, -txt, -tn, TX_TEXT), otherwise the stamp will not be applied.




The texts specified with -tn take priority to the texts that are passed in the header with stamp texts and in the stamp text file.

value With -txt, you specify the following value:

| Value | Description |
|-------------|--|
| <i>file</i> | Name of the text file containing the stamp texts |

default There is no default.

file syntax The stamp text file contains a line with the stamp text for each stamp.



The document, original.pdf, is stamped. The stamp texts are passed in the stamp text file, stamps.txt:

```
pdfstamp -f original.pdf -stp default.stp -db default.db
-txt stamps.txt
```

with stamps.txt:

```
Released
2013-12-03
John Smith
```

related parameters There is a close connection to the following parameters:

| Related Parameter | Page |
|---------------------------------------|------|
| -hed <string> Header with Stamp Texts | 104 |
| -t<n> <string> Stamp Text | 122 |

-uselogicalpage Consider startpagecount

With the **-uselogicalpage** parameter, you specify that the starting page number specified with the **-startpagecount** parameter is taken into account when evaluating the pages to be stamped (**BO_PAGES_TO_STAMP**).

This parameter is optional.

type

With the **BO_PAGES_TO_STAMP** item in the stamp box configuration, you can specify the pages to be stamped.

pages to be stamped

→ *Stamp Layout File (.stp)*, page 130

By default, the actual page numbers of the document are taken when evaluating the pages to be stamped.

default

The document, **original.pdf**, is stamped. The page numbering starts with 4. This is taken into account, when evaluating the pages to be stamped:

```
pdfstamp -f original.pdf -stp default.stp -db default.db
         -txt default.txt -startpagecount 4
```

with **default.stp**:

```
...
BO_PAGES_TO_STAMP = 5
...
```

with **-uselogicalpage** results in:

- The second page of **original.pdf** will be stamped.

without **-uselogicalpage** (default) results in:

- The fifth page of **original.pdf** will be stamped.

There is a close connection to the following parameters:

related parameters

| Related Parameter | Page |
|--|------|
| -startpagecount <integer> Start of the Page Numbering | 125 |

-usepdfaswatermark Stamp As Watermark

purpose With the -usepdfaswatermark parameter, you specify that the stamp template is to be stamped as watermark.

type This parameter is optional.

default By default, the stamp template is applied as stamp.

alternative As an alternative to the specification of the -usepdfaswatermark parameter, you can set the PDF_USE_PDF_AS_WATERMARK environment variable.

 example The document, original.pdf, is stamped as watermark with the stamp template, template.pdf:

```
pdfstamp -f original.pdf -stp template.pdf -usepdfaswatermark
```

related parameters There is a close connection to the following parameters:

| Related Parameter | Page |
|---|------|
| -stp <string> Stamp Layout File or Stamp Template | 120 |

-x <float> Width of the Stamp Template

With the `-x` parameter, you specify how wide the stamp template is to be generated.

This parameter is optional.

With `-x`, you specify the following value:

| Value | Description |
|--------------------|--------------------------------------|
| <code>width</code> | Width of the stamp template in meter |

Default is DIN A4, that means 0.21.

The stamp template, `template.pdf`, will be generated. The width of the stamp template is 4 cm and its height is 6 cm:

```
pdfstamp -o template.pdf -stp default.stp -db default.db
         -txt default.txt -x 0.04 -y 0.06
```

There is a close connection to the following parameters:

| Related Parameter | Page |
|--|------|
| <code>-y <float></code> Height of the Stamp Template | 128 |

-y <float> Height of the Stamp Template


purpose With the -y parameter, you specify how high the stamp template is to be generated.

type This parameter is optional.

value With -y, you specify the following value:

| Value | Description |
|---------------|---------------------------------------|
| <i>height</i> | Height of the stamp template in meter |

default Default is DIN A4, that means 0.297.



The stamp template, template.pdf, will be generated. The width of the stamp template is 4 cm and its height is 6 cm:

```
pdfstamp -o template.pdf -stp default.stp -db default.db
         -txt default.txt -x 0.04 -y 0.06
```

related parameters

There is a close connection to the following parameters:

| Related Parameter | Page |
|--|------|
| -x <float> Width of the Stamp Template | 127 |

8 Configuration - Reference

This chapter describes the following configuration files and settings:

in this chapter

| Configuration File | Page |
|------------------------------|------|
| Stamp Layout File (.stp) | 130 |
| PDF Configuration File (.db) | 149 |
| Flagpage Configuration | 155 |

8.1 Stamp Layout File (.stp)

purpose In the stamp layout file, you configure the layout, the size and the color of the stamp texts and boxes.

PLOSSYS netdome With PLOSSYS netdome, the stamp layout file is configured at the output queue or is passed together with the job files. As basis, you can use the generic stamp layout file, %PLSPLT%\generic.stp.

pdfstamp/pdfstamphft With pdfstamp/pdfstamphft, a stamp layout file must be specified unless a stamp template is used for stamping.

parameter When calling pdfstamp/pdfstamphft, specify the stamp layout file with the -stp parameter.

→ *-stp <string> Stamp Layout File or Stamp Template*, page 120

 **hint - template and examples** A template for the stamp layout file is contained in delivery of pdfstamp/pdfstamphft: %PLSTOOLS%\convcfg\pdfstamp\default.cfg. Many examples of the stamp configuration are found in %PLSTOOLS%\convcfg\pdfstamp\muster.stp.

sections The stamp layout file contains the following items in the following sections:

| Section | Page |
|----------------------------|------|
| Items Without Section | 131 |
| [STAMP_DEFINITION] Section | 132 |
| [text] Section | 133 |
| [box] Section | 137 |
| [SIZE_DEFINITIONS] Section | 145 |

 **example** → *Example of the Stamp Layout File*, page 147

Items Without Section

The items without section in the stamp layout file concern the format-specific stamping. purpose

The [STAMP_DEFINITION] section contains the following items: items

| Item | Description |
|-------------------------------|---|
| TOLERANCE <i>tolerance</i> | <p>Tolerance when the FitExact method is being used for evaluating the paper size for the format-specific stamping</p> <p>Available values for <i>tolerance</i>:</p> <p style="padding-left: 20px;">tolerance in meters</p> <p>Default: none</p> <p> Caution - PLOSSYS netdome: TOLERANCE is only evaluated by pdfstamp/pdfstamphft due to PLOSSYS netdome does not support the format-specific stamping.</p> |
| FIT_EXACT <i>boolean</i> | <p>Method used for evaluating the paper size for the format-specific stamping</p> <p>Available values for <i>boolean</i>:</p> <p style="padding-left: 20px;">NO: The FirstFit method is used. YES: The FitExact method is used.</p> <p>Default: NO</p> <p> Caution - PLOSSYS netdome: TOLERANCE is only evaluated by pdfstamp/pdfstamphft due to PLOSSYS netdome does not support the format-specific stamping.</p> |

[STAMP_DEFINITION] Section

purpose In the [STAMP_DEFINITION] section, you configure the sections for the stamp texts and boxes and the general settings for all stamps.

items The [STAMP_DEFINITION] section contains the following items:

| Item | Description |
|---|--|
| BOX_DEFINITIONS <i>box0 box1 ...</i> | <p>Sections for the stamp boxes</p> <p>Available values for <i>boxn</i>: maximum 100 strings containing maximum 20 characters</p> <p>Default: none</p> |
| COLOR_DEFINITION_n <i>red green blue</i> | <p>RGB value of the color <i>n</i></p> <p>Available values for <i>n</i>: <i>n</i> can be between 0 and 255 and is specified in the stamp texts in TX_COLOR and in stamp boxes in BO_COLOR.</p> <p>Available values for <i>red green blue</i>: three floats between 0.0 and 1.0 for the red, green and blue components of the color</p> <p>Default: none</p> |
| SCALE_STAMP <i>boolean</i> | <p>Are the stamped to be scaled with the document?</p> <p>SCALE_STAMP is used as default for BO_SCALE_BOX.</p> <p>Available values for <i>boolean</i>:</p> <ul style="list-style-type: none"> NO: The stamps will not be scaled. YES: The stamps will be scaled. <p>Default: NO</p> <p> Caution - pdfstamp/pdfstamphft: SCALE_STAMP is only evaluated by PLOSSYS netdome due to pdfstamp/pdfstamphft does not scale.</p> |
| TEXT_DEFINITIONS <i>text0 text1 ...</i> | <p>Sections for the stamp texts</p> <p>Available values for <i>textn</i>: maximum 100 strings containing maximum 20 characters</p> <p>Default: none</p> |

[text] Section

In the [text] section, you configure the properties of the stamp texts with the name *text*. purpose

The [text] section contains the following items:

items

| Item | Description |
|----------------------------------|---|
| TX_ALIGNMENT_HOR <i>align</i> | Horizontal alignment of the stamp text Available values for <i>align</i> : CENTER: centered LEFT: left-aligned RIGHT: right-aligned Default: LEFT |
| TX_ALIGNMENT_VER <i>align</i> | Vertical alignment of the stamp text Available values for <i>align</i> : BASE: base line BOTTOM: bottom line CAP: cap line CENTER: center line TOP: cap height Default: BASE |
| TX_COLOR <i>color</i> | Color of the stamp text Available values for <i>color</i> : integer between 0 and 255; the colors are configured in COLOR_DEFINITION_n: → [STAMP_DEFINITION] Section, page 132 Default: 1, that means Black |
| TX_EXPANSION <i>width</i> | Character width of the stamp text Available values for <i>width</i> : float as factor of the character width specified in the font Default: 1.0 |

..... To be continued

[text] Section, Continuation

items, contd.

The [text] section contains the following items, continuation:

| Item | Description |
|---------------------------------|--|
| TX_FONT <i>font</i> | <p>Font of the stamp text</p> <p>Available values for <i>font</i>:</p> <ul style="list-style-type: none"> GKS font number <p>Default: -2</p> <p> reference - GKS fonts: The GKS fonts and their numbers are described in [FONTS_USR].</p> |
| TX_LINEBREAK <i>boolean</i> | <p>Are line breaks allowed in the stamp text? The line breaks in the stamp text are entered as \n or \r.</p> <p>Available values for <i>boolean</i>:</p> <ul style="list-style-type: none"> N: The text is not wrapped. Y: With \n and \r , the line is broken. <p>Default: N</p> <p> Caution - PLOSSYS netdome: TX_LINEBREAK is not supported by PLOSSYS netdome.</p> |
| TX_LINEDISTANCE <i>distance</i> | <p>Line spacing with multi-line stamp texts</p> <p>Available values for <i>distance</i>:</p> <ul style="list-style-type: none"> float; the unit is meter. <p>Default: 0.0</p> <p> Caution - PLOSSYS netdome: TX_LINEDISTANCE is not supported by PLOSSYS netdome.</p> |

..... *To be continued*

[text] Section, Continuation

The [text] section contains the following items, continuation:

items, contd.

| Item | Description |
|--------------------------|--|
| TX_LWSC <i>width</i> | <p>Line width of the stamp text</p> <p>Available values for <i>width</i>: float; the unit is meter.</p> <p>Default: 0.000254</p> <p> hint - scaling: The line width will be scaled together with the stamp.</p> <p> Caution - render mode FILL: TX_LWSC does not have an effect for a font with the render mode FILL due to only the filling of a character will be displayed.</p> <p>→ <i>Items of the PDF Configuration File</i>, page 150</p> |
| TX_OFFSETX <i>offset</i> | <p>Horizontal distance from the text beginning to the reference point of the stamp box</p> <p>Available values for <i>offset</i>: float; the unit is meter.</p> <p>Default: 0.0</p> |
| TX_OFFSETY <i>offset</i> | <p>Vertical distance from the text beginning to the reference point of the stamp box</p> <p>Available values for <i>offset</i>: float; the unit is meter.</p> <p>Default: 0.0</p> |
| TX_PATH <i>direction</i> | <p>Writing direction of the stamp text</p> <p>Available values for <i>direction</i>:</p> <ul style="list-style-type: none">DOWN: top downLEFT: from the right to the leftRIGHT: from the left to the rightUP: bottom up <p>Default: RIGHT</p> |

..... To be continued

[text] Section, Continuation

items, contd.

The [text] section contains the following items, continuation:

| Item | Description |
|---------------------------|---|
| TX_SIZE <i>size</i> | <p>Text size of the stamp text</p> <p>Available values for <i>size</i>: float; the unit is meter.</p> <p>Default: 0.005</p> |
| TX_SPACING <i>spacing</i> | <p>Space between the characters that is to be inserted in addition to the default space of the font</p> <p>Available values for <i>spacing</i>: float; 1.0 means that the additional spacing corresponds to the height of a capital letter.</p> <p>Default: 0.0</p> |
| TX_TEXT <i>text</i> | <p>Default stamp text unless it is specified explicitly</p> <p>Available values for <i>text</i>: string containing maximum 256 characters</p> <p>Default: none</p> |

[box] Section

In the [box] section, you configure the properties of the stamp box with the name *box*.

purpose

The name *box* of the stamp box must be specified in the BOX_DEFINITIONS item in the [STAMP_DEFINITION] section.

BOX_
DEFINITIONS

→ [STAMP_DEFINITION] Section, page 132

The [box] section contains the following items:

items

| Item | Description |
|---------------------------------------|--|
| BO_ADAPT_TEXT_TO_FRAME <i>boolean</i> | <p>Is the text stamp to be scaled in such a way that it fits into the stamp box specified with BO_HEIGHT and BO_WIDTH exactly.</p> <p>Available values for <i>boolean</i>:</p> <ul style="list-style-type: none">NO: The text stamp will not be scaled.YES: The text stamp will be scaled according to the stamp box. <p>Default: NO</p> <p> Caution - PLOSSYS netdome: BO_ADAPT_TEXT_TO_FRAME is not supported by PLOSSYS netdome.</p> |
| BO_ALIGNMENT_HOR <i>align</i> | <p>Horizontal alignment of the stamp box</p> <p>Available values for <i>align</i>:</p> <ul style="list-style-type: none">CENTER: centeredLEFT: left-alignedRIGHT: right-aligned <p>Default: LEFT</p> |
| BO_ALIGNMENT_VER <i>align</i> | <p>Vertical alignment of the stamp box</p> <p>Available values for <i>align</i>:</p> <ul style="list-style-type: none">BOTTOM: at the bottomCENTER: centeredTOP: at the top <p>Default: TOP</p> |

To be continued

[box] Section, Continuation

items, contd.

The [box] section contains the following items, continuation:

| Item | Description |
|---------------------------------|---|
| BO_ANGLE <i>angle</i> | Angle by which the stamp box is rotated; the reference point for the rotation is the reference point of the stamp which is used for aligning the stamp text. Available values for <i>angle</i> : floats; positive values result in a counter-clockwise rotation. Default: 0 |
| BO_BACKGROUND <i>background</i> | Background of the stamp box Available values for <i>background</i> : BLANKED: The graphic elements of the stamp have a white border within which the document is covered completely. In the other part of the stamp, the document shows through. OPAQUE: The complete stamp including its border covers the document. TRANSPARENT: The document shows through the stamp background. The stamp foreground, that means the stamp text for example, does not show through. Default: TRANSPARENT |
| BO_BORDER <i>boolean</i> | Is a frame to be displayed around the stamp box? Available values for <i>boolean</i> : NO: No frame will be displayed. YES: A frame will be displayed. Default: YES |
| BO_COLOR <i>color</i> | Color of the frame around the stamp box Available values for <i>color</i> : integer between 0 and 255; the colors are configured in COLOR_DEFINITION_n: → [STAMP_DEFINITION] Section, page 132 Default: 1, that means Black |

..... To be continued

[box] Section, Continuation

The [box] section contains the following items, continuation:

items, contd.

| Item | Description |
|---------------------------------------|--|
| BO_CONTENTS <i>text0 text1 ...</i> | <p>Sections of the stamp texts belonging to the stamp box</p> <p>Available values for <i>textn</i>:</p> <ul style="list-style-type: none"> maximum 100 strings containing maximum 20 characters <p>Default: none</p> |
| BO_CREATION <i>method</i> | <p>Method how the stamp is applied onto the document</p> <p>Available values for <i>method</i>:</p> <ul style="list-style-type: none"> GRAY_STAMP: The stamp will be output in Gray onto the document. The brightness of the gray stamp is set by the specified brightness of the text color (see TX_COLOR). STAMP: The stamp will be applied onto the document. WATERMARK: The stamp will be applied as watermark behind the document. Watermarks have the same color as stamps. They only differ in their time of creation. <p>Default: STAMP</p> <p> hint - gray stamp: The layout of the gray stamp will be specified further with the -graystamp parameter when calling pdfstamp/pdfstamphft and by the environment variable PDF_GRAYSTAMP.</p> |
| BO_DISTANCEX <i>distance</i> | <p>Horizontal distance to the position configured by BO_ALIGNMENT_HOR, BO_ALIGNMENT_VER and BO_ROTATE</p> <p>Available values for <i>distance</i>:</p> <ul style="list-style-type: none"> float; the unit is meter. <p>Default: 0.0</p> |

..... To be continued

[box] Section, Continuation

items, contd.

The [box] section contains the following items, continuation:

| Item | Description |
|---------------------------------|---|
| BO_DISTANCEY <i>distance</i> | Vertical distance to the position configured by BO_ALIGNMENT_HOR, BO_ALIGNMENT_VER and BO_ROTATE Available values for <i>distance</i> : float; the unit is meter. Default: 0.0 |
| BO_FRAME <i>file</i> | Name of the graphic file that is applied onto the document as graphic stamp Available values for <i>file</i> : file name; the graphic file must be available in the directory of the stamp layout file *: The graphic file will be passed together with the output job files (PLOSSYS netdome only). → <i>Pass a Graphic File With a Job</i> , page 59 Default: none |
| BO_HEIGHT <i>height</i> | height of the stamp Available values for <i>height</i> : float; the unit is meter. Default: 0.03 |
| BO_LWSC <i>width</i> | Line width of the frame around the stamp box Available values for <i>width</i> : float; the unit is meter. Default: 0.000254 |
| BO_MAXIMIZE <i>boolean</i> | Is the stamp box to be enlarged so that the stamp reaches the document border at one side at least? Available values for <i>boolean</i> : NO: The stamp box will not be enlarged. YES: The stamp box will be enlarged. Default: NO |

..... *To be continued*

[box] Section, Continuation

The [box] section contains the following items, continuation:

items, contd.

| Item | Description |
|-------------------------------------|---|
| BO_OFFSETX <i>offset</i> | Horizontal distance of the frame to the stamp box Available values for <i>offset</i> : float; the unit is meter. Default: 0.0 |
| BO_OFFSETY <i>offset</i> | Vertical distance of the frame to the stamp box Available values for <i>offset</i> : float; the unit is meter. Default: 0.0 |
| BO_ON_SCALEFACTOR <i>min max</i> | Scaling factor of the stamp box; the stamp box will only be displayed if the scaling factor of the document is within the specified range. Available values for <i>min</i> and <i>max</i> : float; the unit is meter. Default: 0.0 1.0  Caution - pdfstamp/pdfstampht: When stamping with pdfstamp/pdfstampht, you have to specified an range that includes 1.0 due to pdfstamp/pdfstampht does not scale. |
| BO_ORIGIN <i>origin</i> | reference point of the stamp box Available values for <i>origin</i> : VISIBLE_AREA: The reference point of the stamp box will be moved to the printable area that means the stamp always appears at the same position of the paper. Default: BO_ORIGIN is deactivated that means that the reference point of the stamp box corresponds to the document borders and the stamp always appears at the same position of the document. |

..... To be continued

[box] Section, Continuation

items, contd.

The [box] section contains the following items, continuation:

| Item | Description |
|----------------------------------|--|
| BO_PAGES_DOMAIN <i>domain</i> | <p>Relation of the pages to be stamped</p> <p>Available values for <i>domain</i>:</p> <ul style="list-style-type: none"> PLOT: The page number relates to the document. SET: The page number relates to the set collation. <p>Default: PLOT</p> <p> Caution - pdfstamp/pdfstamphtf: BO_PAGES_DOMAIN is only evaluated by PLOSSYS netdome due to pdfstamp/pdfstamphtf does not support set collations.</p> |
| BO_PAGES_TO_STAMP <i>page</i> | <p>pages to be stamped</p> <p>Available values for <i>page</i>:</p> <ul style="list-style-type: none"> 0: All pages are stamped. EVEN: The even pages are stamped. FIRST: The first page is stamped. LAST: The last page is stamped. ODD: The odd pages are stamped. xMODy: Each page <i>y</i> starting as of the page <i>x</i> is stamped. x..LAST: All pages as of the page <i>x</i> are stamped. FIRST..x: All pages up to the page <i>x</i> are stamped. x..y: All pages from the page <i>x</i> to the page <i>y</i> are stamped. <p>Default: 0</p> <p> hint - multiple items: Multiple items are separated by comma, for example: BO_PAGES_TO_STAMP „2,3“ BO_PAGES_TO_STAMP „6,8,LAST“ BO_PAGES_TO_STAMP „FIRST,2,LAST“</p> |

To be continued

[box] Section, Continuation

The [box] section contains the following items, continuation:

items, contd.

| Item | Description |
|----------------------------------|---|
| BO REP X <i>min max</i> | Repetition vector in horizontal direction Available values for <i>min</i> and <i>max</i> : float; the unit is meter. Default: 0.0 0.0 |
| BO REP Y <i>min max</i> | Repetition vector in vertical direction Available values for <i>min</i> and <i>max</i> : float; the unit is meter. Default: 0.0 0.0 |
| BO_ROTATE <i>rot</i> | Is the stamp box to be rotated with the document? Available values for <i>rot</i> : NOT_ROTATE: The stamp box will not be rotated. ROTATE: The stamp box will be rotated. Default: ROTATE  Caution - pdfstamp/pdfstamphft: BO_ROTATE is not supported by pdfstamp/pdfstamphft. |
| BO_SCALE_BOX <i>boolean</i> | Is the stamp box to be scaled with the document? Available values for <i>boolean</i> : NO: The stamp box will not be scaled. YES: The stamp box will be scaled. Default: Setting of SCALE_STAMP → [STAMP_DEFINITION] Section, page 132  Caution - pdfstamp/pdfstamphft: BO_SCALE_BOX is not supported by pdfstamp/pdfstamphft. |
| BO_TXT_WIDTH_MIN <i>width</i> | Minimum width of the stamp box Available values for <i>width</i> : float; the unit is meter. Default: The stamp box has the same width as the text contained in it. |

..... To be continued

[box] Section, Continuation

items, contd.

The [box] section contains the following items, continuation:

| Item | Description |
|--------------------------|---|
| BO_WIDTH <i>width</i> | width of the stamp Available values for <i>width</i> : float; the unit is meter. Default: The graphic or the text is displayed in the original size. 72 dpi is used as default resolution for a graphic. |

[SIZE_DEFINITIONS] Section

In the optional [SIZE_DEFINITIONS] section, you configure the formats valid for the format-specific stamp configurations.

purpose

The [SIZE_DEFINITIONS] section is not supported by PLOSSYS netdome, that means format-specific stamping is only available with pdfstamp/pdfstamphft.

 **Caution** - not PLOSSYS net-dome


The [SIZE_DEFINITIONS] section contains the following items:

items

| Item | Description |
|----------------------------|--|
| <i>format width height</i> | <p>Format with width and height</p> <p>Available values for <i>format</i>:</p> <p>any string; is used as prefix for the format-specific sections.</p> <p>Available values for <i>width</i> and <i>height</i>:</p> <p>float; the unit is meter.</p> <p>Default: none</p> <p>If the paper size of a document corresponds to one of the formats using the specified comparison method (FIT_EXACT) and the specified tolerance (TOLERANCE), the stamp settings are taken from the format-specific section:</p> <p>[<i>format\STAMP_DEFINITION</i>] [<i>format\text</i>] [<i>format\box</i>]</p> <p>Otherwise, the defaults from the sections without <i>format</i> are used.</p> |

..... *To be continued*

[SIZE_DEFINITIONS] Section, Continuation




[SIZE_DEFINITIONS] section in the stamp layout file:

```
[SIZE_DEFINITIONS]
DINA4_P 0.210 0.297
DINA4_L 0.297 0.210
DINA3_P 0.297 0.420
DINA3_L 0.420 0.297
...
[DINA4_P\STAMP_DEFINITION]
...
[DINA4_P\Text_0]
...
[DINA4_P\Box_0]
...
[DINA4_L\STAMP_DEFINITION]
...
[DINA4_L\Text_0]
...
[DINA4_L\Box_0]
...
```

Example of the Stamp Layout File

```
# ======  
# ----- Stamp Definition Section -----  
# ======  
  
[STAMP_DEFINITION]  
TEXT_DEFINITIONS      Text_0 Text_1  
BOX_DEFINITIONS       Box_0 Box_1 Box_2 Box_3  
COLOR_DEFINITION_2    1.0 0.5 0.0  
COLOR_DEFINITION_3    0.0 0.5 1.0  
SCALE_STAMP           YES  
# ======  
# ----- Text Sections -----  
# ======  
  
[Text_0]  
TX_SIZE               0.004  
TX_COLOR              1  
TX_FONT               -2  
TX_LWSC               0.0004  
TX_OFFSETX            0.0  
TX_OFFSETY            0.0075  
TX_SPACING             0.0  
TX_EXPANSION          2.0  
TX_ALIGNMENT_HOR       CENTER  
TX_ALIGNMENT_VER       BASE  
TX_PATH                RIGHT  
  
[Text_1]  
TX_SIZE               0.007  
TX_COLOR              1  
TX_FONT               -10001  
TX_LWSC               0.0002  
TX_OFFSETX            0.0  
TX_OFFSETY            0.0000  
TX_SPACING             0.0  
TX_EXPANSION          2.0  
TX_ALIGNMENT_HOR       CENTER  
TX_ALIGNMENT_VER       BASE  
TX_PATH                RIGHT  
# ======  
# ----- Box Definition Section -----  
# ======  
  
[Box_0]  
BO_CONTENTS           Text_0  
BO_ALIGNMENT_HOR      LEFT  
BO_ALIGNMENT_VER      BOTTOM  
BO_ROTATE              ROTATE  
BO_ANGLE                10.0  
BO_DISTANCEX           0.02  
BO_DISTANCEY           0.00  
BO_OFFSETX             0.002  
BO_OFFSETY             0.002  
BO_BORDER               Y  
BO_COLOR                1  
BO_LWSC                0.001  
BO_BACKGROUND          TRANSPARENT  
BO_CREATION             STAMP  
BO_REP_X               0.000000 0.000000  
BO_REP_Y               0.000000 0.000000  
BO_MAXIMIZE             NO  
BO_ON_SCALEFACTOR     0.0 99.9
```



To be continued

Example of the Stamp Layout File, Continuation

 example,
continuation

```
[Box_1]
BO_CONTENTS Text_1
BO_ALIGNMENT_HOR CENTER
BO_ALIGNMENT_VER TOP
BO_ROTATE ROTATE
BO_ANGLE 0.0
BO_DISTANCEX 0.00
BO_DISTANCEY 0.005
BO_OFFSETX 0.002
BO_OFFSETY 0.001
BO_BORDER Y
BO_COLOR 2
BO_LWSC 0.0002
BO_BACKGROUND OPAQUE
BO_CREATION STAMP
BO REP_X 0.000000 0.000000
BO REP_Y 0.000000 0.000000
BO_MAXIMIZE NO
BO_ON_SCALEFACTOR 0.0 99.9

[Box_2]
BO_ALIGNMENT_HOR LEFT
BO_ALIGNMENT_VER CENTER
BO_ROTATE ROTATE
BO_ANGLE 0.0
BO_DISTANCEX 0.05
BO_DISTANCEY 0.00
BO_OFFSETX 0.002
BO_OFFSETY 0.002
BO_BORDER Y
BO_COLOR 1
BO_LWSC 0.0002
BO_BACKGROUND TRANSPARENT
BO_CREATION STAMP
BO REP_X 0.000000 0.000000
BO REP_Y 0.000000 0.000000
BO_MAXIMIZE N
BO_ON_SCALEFACTOR 0.0 99.9
BO_FRAME seallogo.met
BO_WIDTH 0.06
BO_HEIGHT 0.06

[Box_3]
BO_ALIGNMENT_HOR RIGHT
BO_ALIGNMENT_VER BOTTOM
BO_ROTATE ROTATE
BO_ANGLE 30
BO_DISTANCEX 0.00
BO_DISTANCEY 0.07
BO_OFFSETX 0.002
BO_OFFSETY 0.002
BO_BORDER N
BO_COLOR 1
BO_LWSC 0.0002
BO_BACKGROUND TRANSPARENT
BO_CREATION WATERMARK
BO REP_X 0.10 0.05
BO REP_Y 0.06 0.12
BO_MAXIMIZE N
BO_ON_SCALEFACTOR 0.0 99.9
BO_FRAME seallogo.met
BO_WIDTH 0.06
BO_HEIGHT 0.06
```

8.2 PDF Configuration File (.db)

| | |
|---|---|
| In the PDF configuration file, you configure the settings for the PDF generation. | purpose |
| With PLOSSYS netdome, the PDF configuration file is configured at the output queue. | PLOSSYS net-dome |
| With pdfstamp/pdfstamphft, the PDF configuration file must be specified. | pdfstamp/ pdfstamphft |
| The PDF configuration file is specified with the -db parameter when calling pdfstamp/pdfstamphft. | parameter |
| → <i>-db <string> PDF Configuration File</i> , page 97 | |
| → <i>Items of the PDF Configuration File</i> , page 150 | items |
| → <i>Example of the PDF Configuration File</i> , page 154 |  example |

Items of the PDF Configuration File

items

The PDF configuration file contains the following items:

| Item | Description |
|---|--|
| PDF.Author: <i>author</i> | <p>Entry for the document property Author in the PDF file</p> <p>Available values for <i>author</i>: any string</p> <p>Default: none</p> |
| PDF.colour: <i>n red green blue name</i> | <p>Color definition</p> <p>Available values for <i>n</i>: <i>n</i> can be between 0 and 16 and is specified in the stamp texts in TX_COLOR and in stamp boxes in BO_COLOR.</p> <p>Available values for <i>red green blue</i>: three floats between 0.0 and 1.0 for the red, green and blue components of the color</p> <p>Available values for <i>name</i>: any string as color name</p> <p>Default: Color table from default.db</p> |
| PDF.color_available: <i>boolean</i> | <p>How are the colors to be displayed in the PDF file?</p> <p>Available values for <i>boolean</i>: NO: The colors are displayed as grayscale. YES: The colors are displayed as colors.</p> <p>Default: YES</p> |
| PDF.compression: <i>boolean</i> | <p>Is the FlatDecode compression method to be used?</p> <p>Available values for <i>boolean</i>: NO: The file will not be compressed. YES: The file will be compressed using Flat-Decode.</p> <p>Default: NO</p> |

..... To be continued

Items of the PDF Configuration File, Continuation

The PDF configuration file contains the following items, continuation:

items, contd.

| Item | Description |
|---|---|
| PDF.Creator: <i>creator</i> | <p>Entry for the document property Creator in the PDF file</p> <p>Available values for <i>creator</i>:</p> <ul style="list-style-type: none">any string <p>Default: none</p> |
| PDF.font: <i>nr name render object</i> | <p>Font definition</p> <p>Available values for <i>nr</i>:</p> <ul style="list-style-type: none">integer; will be specified in TX_FONT for the stamp texts. <p>Available values for <i>name</i>:</p> <ul style="list-style-type: none">any string for the font name <p>Available values for <i>render</i>:</p> <ul style="list-style-type: none">FILL: The filling of the characters is displayed.FILLSTROKE: The filling and the line of the characters are displayed.INVISIBLE: The characters are invisible.STROKE: The line of the characters is displayed. <p>Available values for <i>object</i>:</p> <ul style="list-style-type: none">Name of the font file <p>Default: none</p> <p> hint - directory: The fonts must be available in the SEAL-FONTS\pdo directory.</p> |

..... To be continued

Items of the PDF Configuration File, Continuation

items, contd.

The PDF configuration file contains the following items, continuation:

| Item | Description |
|---------------------------------------|--|
| PDF.gray_available: <i>boolean</i> | <p>How are the grayscales to be displayed in the PDF file</p> <p>Available values for <i>boolean</i>:</p> <ul style="list-style-type: none"> NO: The grayscales are displayed in Black and White. YES: The grayscales are displayed as grayscales. <p>Default: YES</p> <p> hint - PDF.color_available:</p> <p>PDF.color_available takes priority that means PDF.gray_available will only be evaluated if PDF.color_available: NO has been specified.</p> |
| PDF.Keywords: <i>keywords</i> | <p>Entry for the document property Keywords in the PDF file</p> <p>Available values for <i>keywords</i>:</p> <ul style="list-style-type: none"> any string <p>Default: none</p> |
| PDF.precision: <i>prec</i> | <p>Number of decimal places used in coordinates</p> <p>Available values for <i>prec</i>:</p> <ul style="list-style-type: none"> integer <p>Default: 0</p> |
| PDF.Producer: <i>producer</i> | <p>Entry for the document property Producer in the PDF file</p> <p>Available values for <i>producer</i>:</p> <ul style="list-style-type: none"> any string <p>Default: none</p> |
| PDF.resolution: <i>res</i> | <p>Resolution of the internal coordinates</p> <p>Available values for <i>res</i>:</p> <ul style="list-style-type: none"> integer <p>Default: 600</p> |

To be continued

Items of the PDF Configuration File, Continuation

The PDF configuration file contains the following items, continuation:

items, contd.

| Item | Description |
|-----------------------------|--|
| PDF.Subject: <i>subject</i> | Entry for the document property Subject in the PDF file Available values for <i>subject</i> : any string Default: none |
| PDF.Title: <i>title</i> | Entry for the document property Title in the PDF file Available values for <i>title</i> : any string Default: none |
| PDF.type: <i>version</i> | Is the PDF file to be generated conform to PDF/A? Available values for <i>version</i> : PDFA: The file will be generated conform to PDF/A 1b. PDF: The file will be generated as "normal" PDF file. Default: PDF |
| PDF.Version: <i>version</i> | The PDF file is to be generated in which PDF version? Available values for <i>version</i> : 1.n: The file will be generated in PDF 1.n. Default: 1.4 |

Example of the PDF Configuration File



```

#-----
PDF.Version:      1.4
#-----
PDF.precision: 0
PDF.resolution: 600
PDF.compression: Yes
#-----
PDF.colour_available: YES
#-----
PDF.colour: 0 1.0      1.0      1.0      white
PDF.colour: 1 0.0      0.0      0.0      black
PDF.colour: 2 1.0      0.0      0.0      red
PDF.colour: 3 0.0      1.0      0.0      green
PDF.colour: 4 0.0      0.0      1.0      blue
PDF.colour: 5 0.0      1.0      1.0      cyan
PDF.colour: 6 1.0      0.0      1.0      magenta
PDF.colour: 7 1.0      1.0      0.0      yellow
PDF.colour: 8 0.33     0.33     0.33     dark grey
PDF.colour: 9 0.66     0.66     0.66     light grey
PDF.colour: 10 1.00    0.5      0.0      orange
PDF.colour: 11 0.0      1.0      0.5      turquoise
PDF.colour: 12 0.5      0.0      1.0      purple
PDF.colour: 13 0.0      0.5      1.0      light blue
PDF.colour: 14 1.0      0.0      0.5      wine red
PDF.colour: 15 0.5     1.0      0.0      grass green
#-----
PDF.font:   -1001 Helvetica FILL helvetica.pdo
PDF.font:   -1002 Courier FILL courier.pdo
PDF.font:   -1003 Times-Roman FILL times.pdo
PDF.font:   -1004 Symbol FILL symbol.pdo
PDF.font:   -1005 Helvetica-Bold FILL helvetica_bold.pdo
PDF.font:   -1006 Helvetica-BoldOblique FILL helvetica_boldoblique.pdo
PDF.font:   -1007 Helvetica-Oblique FILL helvetica_oblique.pdo
PDF.font:   -1008 Courier-Bold FILL courier_bold.pdo
PDF.font:   -1009 Courier-BoldOblique FILL courier_boldoblique.pdo
PDF.font:   -1010 Courier-Oblique FILL courier_oblique.pdo
PDF.font:   -1011 Times-Bold FILL times.pdo
PDF.font:   -1012 Times-BoldItalic FILL times_bolditalic.pdo
PDF.font:   -1013 Times-Italic FILL times_italic.pdo
PDF.font:   -2001 Helvetica STROKE helvetica.pdo
PDF.font:   -2002 Courier STROKE courier.pdo
PDF.font:   -3001 Helvetica FILLSTROKE helvetica.pdo
PDF.font:   -3002 Courier FILLSTROKE courier.pdo
PDF.font:   -4001 Helvetica INVISIBLE helvetica.pdo
PDF.font:   -4002 Courier INVISIBLE courier.pdo
#-----
PDF.Title:    "PDF Document"
PDF.Author:   "SEAL Systems"
PDF.Creator:  "pdftools"
PDF.Producer: "pdfstamp"
PDF.Subject:  "PDF document created by pdfstamp"
PDF.Keywords:  " "

```

8.3 Flagpage Configuration

With the flagpage configuration settings, you configure the position and the layout of the flagpage.

With PLOSSYS netdome, you specify the settings for the flagpage in the plossys.cfg configuration file.

PLOSSYS net-dome

With pdfstamp/pdfstamphft, you specify the settings for the flagpage in a flag-page configuration file.

pdfstamp/
pdfstamphft

The flagpage configuration file is specified with the -fp parameter when calling pdfstamp/pdfstamphft.

parameter

→ *-fp <string> Flagpage Configuration File*, page 100

→ *Flagpage Configuration Settings*, page 156

items

→ *Example of the Flagpage Configuration Settings*, page 160

 example

Flagpage Configuration Settings

settings

The following flagpage configuration settings are available:

| Item | Description |
|---------------------------------|--|
| FP_ALIGNMENT <i>align</i> | <p>Horizontal alignment of the flagpage; in addition to FP_SIDE, the flagpage can be positioned at every document corner this way.</p> <p>Available values for <i>align</i>:</p> <ul style="list-style-type: none"> CENTER: centered LEFT: left-aligned RIGHT: right-aligned <p>Default: CENTER</p> |
| FP_CLEARBG <i>boolean</i> | <p>Is the background of the flagpage to be cleared?</p> <p>Available values for <i>boolean</i>:</p> <ul style="list-style-type: none"> NO: The background will not be cleared. YES: The background will be cleared. <p>Default: NO</p> |
| FP_COLOR <i>color</i> | <p>Color of the flagpage text</p> <p>Available values for <i>color</i>:</p> <ul style="list-style-type: none"> integer between 0 and 255; the colors are configured in COLOR_DEFINITION_n in the stamp layout file: → [STAMP_DEFINITION] Section, page 132 <p>Default: 1, that means Black</p> |
| FP_DISTANCEX <i>distance</i> | <p>Horizontal distance to the document border</p> <p>Available values for <i>distance</i>:</p> <ul style="list-style-type: none"> float; the unit is meter. <p>Default: 0.0</p> |
| FP_DISTANCEY <i>distance</i> | <p>Vertical distance to the document border</p> <p>Available values for <i>distance</i>:</p> <ul style="list-style-type: none"> float; the unit is meter. <p>Default: 0.0</p> |

..... To be continued

Flagpage Configuration Settings, Continuation

The following flagpage configuration settings are available, contd.:

settings, continuation

| Item | Description |
|-----------------------------|---|
| FP_FONT <i>font</i> | <p>Font of the flagpage text</p> <p>Available values for <i>font</i>:</p> <ul style="list-style-type: none"> GKS font number <p>Default: -2</p> <p> reference - GKS fonts: The GKS fonts and their numbers are described in [FONTS_USR].</p> |
| FP_GENERATE <i>generate</i> | <p>When is the flagpage to be created?</p> <p>Available values for <i>generate</i>:</p> <ul style="list-style-type: none"> ALLOWED: The flagpage will be generated dependent on the header item. EVER: The flagpage will always be generated independent of the header item. NEVER: The flagpage will never be generated independent of the header item. <p>Default: ALLOWED</p> <p> Caution - pdfstamp/pdfstamphft: FP_GENERATE is not supported by pdfstamp/pdfstamphft.</p> |
| FP_LINEWIDTH <i>width</i> | <p>Line width of the stamp text</p> <p>Available values for <i>width</i>:</p> <ul style="list-style-type: none"> float; the unit is meter. <p>Default: 0.0003</p> |
| FP_POSITION <i>position</i> | <p>Position of the flagpage referring to the document border</p> <p>Available values for <i>position</i>:</p> <ul style="list-style-type: none"> INSIDE: The flagpage will be applied inside the document border. OPTIONAL_OUTSIDE: The flagpage will be applied outside the document if this is possible without scaling the document, otherwise, it will be applied inside. OUTSIDE: The flagpage will be applied outside the document border. If required, the document is scaled or clipped dependent on the scaling type. <p>Default: OUTSIDE</p> |

..... To be continued

Flagpage Configuration Settings, Continuation

settings, continuation

The following flagpage configuration settings are available, contd.:

| Item | Description |
|---------------------------|---|
| FP_ROTATE <i>rot</i> | <p>Is the flagpage to be rotated with the document?</p> <p>Available values for <i>rot</i>:</p> <ul style="list-style-type: none"> NOT_ROTATE: The flagpage will not be rotated. ROTATE: The flagpage will be rotated. <p>Default: ROTATE</p> <p> Caution - pdfstamp/pdfstamphft: FP_ROTATE is not supported by pdfstamp/pdfstamphft.</p> |
| FP_SIDE <i>side</i> | <p>Document border where the flagpage is output; in addition to FP_ALIGNMENT, the flagpage can be positioned at every document corner this way.</p> <p>Available values for <i>side</i>:</p> <ul style="list-style-type: none"> BOTTOM: document border at the bottom LEFT: document border at the left RIGHT: document border at the right TOP: document border at the top <p>Default: BOTTOM</p> |
| FP_SPACING <i>spacing</i> | <p>Character spacing of the flagpage text</p> <p>Available values for <i>spacing</i>:</p> <ul style="list-style-type: none"> float; 1.0 means that the additional spacing corresponds to the height of a capital letter. <p>Default: 0.0</p> |
| FP_TEXTSIZE <i>size</i> | <p>Text size of the flagpage</p> <p>Available values for <i>size</i>:</p> <ul style="list-style-type: none"> float; the unit is meter. <p>Default: 0.003</p> |

..... To be continued

Flagpage Configuration Settings, Continuation

The following flagpage configuration settings are available, contd.:

settings, continuation

| Item | Description |
|-----------------------------------|--|
| FP_UPVECTOR <i>orientation</i> | <p>Orientation of the flagpage</p> <p>Available values for <i>orientation</i>:</p> <ul style="list-style-type: none">IN: The flagpage can be read when looking from outside to the document center.NONE: The flagpage at the left or the right border can be read from the right, the flagpage at the top or the bottom border, can be read from the bottom.OUT: The flagpage can be read when looking from the document center outwards. <p>Default: IN</p> <p> Caution - pdfstamp/pdfstamphft: FP_UPVECTOR is not supported by pdfstamp/pdfstamphft.</p> |

Example of the Flagpage Configuration Settings

 example

```
FP_POSITION      OUTSIDE
FP_SIDE          RIGHT
FP_ALIGNMENT     CENTER
FP_COLOR         2
FP_DISTANCEX    0.001
FP_DISTANCEY    0.001
FP_FONT          -855
FP_LINEWIDTH     0.0005
FP_SPACING       0.000
FP_TEXTSIZE      0.003
FP_CLEARBG       N
```

Appendix A Examples of the Stamp Layout File

This chapter deals with the following topics:

in this chapter

| Topic | Page |
|---|------|
| Colored Graphic Stamp Top Left | 162 |
| Red Text Stamp Across the Document | 164 |
| Transparent, Two-Line Text Stamp Bottom Right | 166 |
| Gray Text Stamp Center | 168 |
| Graphic Stamp As Watermark With Repetition | 170 |
| Stamp Mirrored Top Center | 172 |

Colored Graphic Stamp Top Left

stamp layout file


Extract of the stamp layout file:

```
[STAMP_DEFINITION]
  TEXT_DEFINITIONS      Text_5
  BOX_DEFINITIONS       Box_0
  COLOR_DEFINITION_2    1.0 0.5 0.0
  COLOR_DEFINITION_3    0.0 0.5 1.0
  SCALE_STAMP           NO

[Box_0]
  BO_ALIGNMENT_HOR      LEFT
  BO_ALIGNMENT_VER      TOP
  BO_ROTATE              ROTATE
  BO_ANGLE                0.0
  BO_DISTANCEX            0.020
  BO_DISTANCEY            0.030
  BO_OFFSETX               0.000
  BO_OFFSETY               0.000
  BO_BORDER                  Y
  BO_COLOR                   1
  BO_LWSC                    0.001
  BO_BACKGROUND             TRANSPARENT
  BO_CREATION                 STAMP
  BO_FRAME                     seal_logo.met
  BO_WIDTH                      0.08
  BO_HEIGHT                      0.02
```

To be continued

Colored Graphic Stamp Top Left, Continuation



Red Text Stamp Across the Document

stamp layout file

Extract of the stamp layout file:


```
[STAMP_DEFINITION]
    TEXT_DEFINITIONS      Text_0
    BOX_DEFINITIONS       Box_2
    COLOR_DEFINITION_2   1.0 0.0 0.0
    SCALE_STAMP           YES

[Text_0]
    TX_SIZE               0.010
    TX_COLOR              2
    TX_FONT               -401
    TX_LWSC                0.0004
    TX_OFFSETX             0.0
    TX_OFFSETY             0.0075
    TX_SPACING              0.0
    TX_EXPANSION            2.0
    TX_ALIGNMENT_HOR        CENTER
    TX_ALIGNMENT_VER        BASE
    TX_PATH                 RIGHT

[Box_2]
    BO_CONTENTS           Text_0
    BO_ALIGNMENT_HOR      CENTER
    BO_ALIGNMENT_VER      CENTER
    BO_ROTATE               ROTATE
    BO_ANGLE                  25.0
    BO_DISTANCEX             0.000
    BO_DISTANCEY             0.000
    BO_OFFSETX                0.002
    BO_OFFSETY                0.002
    BO_BORDER                  Y
    BO_COLOR                   2
    BO_LWSC                     0.001
    BO_BACKGROUND             BLANKED
    BO_CREATION                STAMP
```

To be continued

Red Text Stamp Across the Document, Continuation



Transparent, Two-Line Text Stamp Bottom Right

stamp layout file

Extract of the stamp layout file:

```
[STAMP_DEFINITION]
    TEXT_DEFINITIONS          Text_1  Text_2
    BOX_DEFINITIONS           Box_1
    COLOR_DEFINITION_2        1.0 0.0 0.0
    COLOR_DEFINITION_3        0.7 0.7 0.7
    SCALE_STAMP                YES

[Text_1]
    TX_SIZE                  0.004
    TX_COLOR                 3
    TX_FONT                  -501
    TX_LWSC                  0.0004
    TX_OFFSETX               0.0
    TX_OFFSETY               0.0075
    TX_SPACING                0.0
    TX_EXPANSION              2.0
    TX_ALIGNMENT_HOR          CENTER
    TX_ALIGNMENT_VER          TOP
    TX_PATH                   RIGHT


[Text_2]
    TX_SIZE                  0.002
    TX_COLOR                 3
    TX_FONT                  -401
    TX_LWSC                  0.0004
    TX_OFFSETX               0.0
    TX_OFFSETY               0.0075
    TX_SPACING                0.0
    TX_EXPANSION              2.0
    TX_ALIGNMENT_HOR          CENTER
    TX_ALIGNMENT_VER          BASE
    TX_PATH                   RIGHT

[Box_1]
    BO_CONTENTS             Text_1  Text_2
    BO_ALIGNMENT_HOR         RIGHT
    BO_ALIGNMENT_VER         BOTTOM
    BO_ROTATE                 ROTATE
    BO_ANGLE                  -15.0
    BO_DISTANCEX              0.05
    BO_DISTANCEY              0.06
    BO_OFFSETX                0.002
    BO_OFFSETY                0.002
    BO_BORDER                  Y
    BO_COLOR                  3
    BO_LWSC                  0.001
    BO_BACKGROUND              TRANSPARENT
    BO_CREATION                STAMP
```

To be continued

Transparent, Two-Line Text Stamp Bottom Right,

Continuation



Gray Text Stamp Center

stamp layout file

Extract of the stamp layout file:


```
[STAMP_DEFINITION]
  TEXT_DEFINITIONS      Text_5
  BOX_DEFINITIONS       Box_1
  COLOR_DEFINITION_3    0.7 0.7 0.7
  SCALE_STAMP           YES

[Text_5]
  TX_SIZE                0.008
  TX_COLOR               3
  TX_FONT                -401
  TX_LWSC                0.0004
  TX_OFFSETX              0.0
  TX_OFFSETY              0.0075
  TX_SPACING              0.0
  TX_EXPANSION             1.0
  TX_ALIGNMENT_HOR        CENTER
  TX_ALIGNMENT_VER        TOP
  TX_PATH                 RIGHT

[Box_1]
  BO_CONTENTS            Text_5
  BO_ALIGNMENT_HOR        CENTER
  BO_ALIGNMENT_VER        CENTER
  BO_ROTATE                ROTATE
  BO_ANGLE                  00.0
  BO_DISTANCEX              0.002
  BO_DISTANCEY              0.002
  BO_OFFSETX                0.002
  BO_OFFSETY                0.002
  BO_BORDER                  Y
  BO_COLOR                   3
  BO_LWSC                    0.001
  BO_BACKGROUND              TRANSPARENT
  BO_CREATION                GRAY_STAMP
```

To be continued

Gray Text Stamp Center, Continuation



Graphic Stamp As Watermark With Repetition


stamp layout file

Extract of the stamp layout file:

```
[STAMP_DEFINITION]
  BOX_DEFINITIONS          Box_6
  SCALE_STAMP               NO
[Box_6]
  BO_ALIGNMENT_HOR         RIGHT
  BO_ALIGNMENT_VER         BOTTOM
  BO_ROTATE                ROTATE
  BO_ANGLE                 10.0
  BO_DISTANCEX              0.00
  BO_DISTANCEY              0.07
  BO_OFFSETX                0.002
  BO_OFFSETY                0.002
  BO_BORDER                  N
  BO_COLOR                   1
  BO_LWSC                    0.002
  BO_BACKGROUND              TRANSPARENT
  BO_CREATION                WATERMARK
  BO_FRAME                  seal_logo.met
  BO_WIDTH                   0.03
  BO_HEIGHT                  0.03
  BO REP_X                  0.15 0.10
  BO REP_Y                  0.15 0.06
```

To be continued

Graphic Stamp As Watermark With Repetition, Continuation



Stamp Mirrored Top Center

stamp layout file

Extract of the stamp layout file:


```
[STAMP_DEFINITION]
    TEXT_DEFINITIONS      Text_9
    BOX_DEFINITIONS       Box_6
    COLOR_DEFINITION_2   1.0 0.5 0.0
    SCALE_STAMP           NO

[Text_9]
    TX_SIZE                0.005
    TX_COLOR               2
    TX_FONT                -401
    TX_LWSC                0.0004
    TX_OFFSETX              0.0
    TX_OFFSETY              0.0075
    TX_SPACING              -0.5
    TX_EXPANSION             -2.0
    TX_ALIGNMENT_HOR        CENTER
    TX_ALIGNMENT_VER        BASE
    TX_PATH                 RIGHT

[Box_6]
    BO_CONTENTS            Text_9
    BO_ALIGNMENT_HOR        CENTER
    BO_ALIGNMENT_VER        TOP
    BO_ROTATE                ROTATE
    BO_ANGLE                  0.0
    BO_DISTANCEX              0.07
    BO_DISTANCEY              0.02
    BO_OFFSETX                0.002
    BO_OFFSETY                0.002
    BO_BORDER                  N
    BO_COLOR                   1
    BO_LWSC                    0.001
    BO_BACKGROUND              OPAQUE
    BO_CREATION                STAMP
```

To be continued

Stamp Mirrored Top Center, Continuation



Bibliography

| | |
|---------------------|--|
| [FONTS_USR] | <i>SEALFONTS - Character Set Package</i> , User Manual, SEAL Systems |
| [NETDOME_TEC] | <i>PLOSSYS netdome</i> , System Description, SEAL Systems |
| [PDF_REF] | <i>PDF Reference</i> , Version 1.7, Adobe Systems Incorporated |
| [PDFTOOLS_TEC] | <i>PDF Tools</i> , System Description, SEAL Systems |
| [PLOSSYS_PARAM_TEC] | <i>PLOSSYS Job Parameter</i> , System Description, SEAL Systems |
| [TIFFSTAMP_TEC] | <i>TIFF Tools - TIFF Stamp</i> , System Description, SEAL Systems |

Terminology

Adobe Acrobat Reader

| | |
|-----------------|---|
| Inscription | Product from Adobe Systems for viewing PDF files →Flagpage |
| Flagpage | Lettering line in the margin of the document |
| Header | File in ASCII format that contains items for configuring an output job for →PLOSSYS netdome |
| PDF Collection | contains one or more files. The embedded files may contain additional describing information (for example, sender, receiver, e-mail subject) which are displayed by Adobe Acrobat Reader in the search. PDF collections may contain folder structure information. The main file serves as cover sheet and contains the description of the additional information. |
| PDF Portfolio | corresponds to a PDF collection whose main file is only a dummy. |
| PLOSSYS netdome | Output management system from SEAL Systems |
| Stamp | Graphic element which is applied onto the document |
| UserUnit | →Adobe Acrobat Reader can only display PDF files up to a size of 14400 units (200 inch). If a UserUnit is set in the PDF file, all internal metric coordinates are divided by the value of the UserUnit. Because →Adobe Acrobat Reader and other viewers evaluate the UserUnit, the correct size is identified further on. |
| Watermark | Stamp applied as watermark behind the document |

Abbreviations

| | |
|-------|--|
| ASCII | American Standard Code for Information Interchange |
| DIN | German Institute of Standardization |
| GKS | Graphic Kernel System |
| HFT | Host Function Table |
| ISO | International Standards Organization |
| JPEG | Joint Photographic Experts Group |
| PDF | Adobe Portable Document Format |
| PDF/A | Adobe Portable Document Format |
| PNG | Portable Network Graphics |
| RGB | Red Green Blue |
| TIFF | Tagged Image File Format |
| XFA | XML Forms Architecture |
| XML | Extensible Markup Language |

Index

Symbols

%DATE% 67
%DATEDE% 67
%DATEDEYY% 67
%DATEUS% 67
%DATEUSYY% 67
%PAGE% 67, 69, 118
%PAGES% 67, 69

A

Adobe Acrobat Reader 175
Adobe stamp 73
Adobe stamp, delete 96
-af 74, 94
alignment, stamp text 41
ALLOWED 157
ASCII 176
associated 51
automatic repairing 14

B

background
 graphic stamp 32
 stamp 32
 transparent 116
BASE 41, 133
BLANKED 32, 138
BO_ALIGNMENT_HOR 24, 137
BO_ALIGNMENT_VER 24, 137
BO_ANGLE 38, 138
BO_BACKGROUND 32, 34, 138
BO_BORDER 34, 36, 138
BO_COLOR 36, 138
BO_CONTENTS 22, 23, 43, 139
BO_CREATION 27, 28, 29, 30, 31, 102, 139
BO_DISTANCEX 25, 139
BO_DISTANCEY 25, 140
BO_FRAME 23, 59, 140
BO_HEIGHT 140
BO_LWSC 36, 140
BO_MAXIMIZE 140
BO_OFFSETX 36, 141
BO_OFFSETY 36, 141
BO_ON_SCALEFACTOR 141
BO_ORIGIN 25, 141
BO_PAGES_DOMAIN 58, 142
BO_PAGES_TO_STAMP 39, 125, 142
BO REP_X 44, 143
BO REP_Y 44, 143

BO_ROTATE 55, 143
BO_SCALE_BOX 55, 143
BO_TXT_WIDTH_MIN 143
BO_WIDTH 144
BOTTOM 24, 41, 133, 137, 158
BOX_DEFINITIONS 22, 132, 137

C

CAP 41, 133
CENTER 24, 41, 133, 137, 156
character width 46
color 28, 102
COLOR_DEFINITION_n 132, 133, 138, 156
color, frame 36
configuration 14
conformance level 87

D

-d 73, 95
-da 96
Date 67
-db 63, 97
default for stamp text 40
delete
 Adobe stamp 96
 stamp 73, 95
 temporary stamp file 107
DIN 176
distance, stamp template 111
DOWN 135

E

environment variable
 PDF_DATE_FORMAT 67
 PDF_GRAYSTAMP 28, 29, 30, 139
 PLS_STAMP_MAX 15
 SEAL_DEFAULTCODEPAGE 18
 SEALFONTS 18
 SEALRESOURCEPATH 71

EVEN 142
even 112
EVER 157

F

-f 98
FILL 135, 151
FILLSTROKE 151
FIRST 142
FIRST..x 142
FirstFit 78

FIT_EXACT 78, 131

FitExact 78

flagpage 16, 175

- configuration file 100

- configuration settings 155

- pdfstamp** 76

- PLOSSYS netdome 61

- text 101

-forcepd़fa 71, 87, 99

format-specific stamp 78

-fp 76, 100, 155

FP_ALIGNMENT 156

FP_CLEARBG 156

FP_COLOR 156

FP_DISTANCEX 156

FP_DISTANCEY 156

FP_FONT 157

FP_GENERATE 76, 157

FP_LINEWIDTH 157

FP_POSITION 157

FP_ROTATE 158

FP_SIDE 158

FP_SPACING 158

FP_TEXTESIZE 158

FP_UPVECTOR 76, 159

-fptxtn 76, 101

frame 36

front and back side 57

G

GKS 176

GKS font 134

GKS metafile 19

- variable 60

GKSM 60

graphic file

- pass 59

graphic format for graphic stamp 19

graphic stamp 19

- background 32

- configure 23

- graphic format 19

- pass graphic file 59

graphical user interface 14

gray 29, 102

GRAY_STAMP 28, 29, 30, 139

grayscale 29

gray-simulated 16, 30

-graystamp 29, 30, 102

group stamp texts 43

H

-h 103

header 53, 65, 104, 175

- information 47

-hed 65

height of stamp template 128

HFT 14, 176

I

-i 84, 85, 105

ICC file 71, 87

IN 159

input file 98

inscription, see **flagpage**

INSIDE 157

interface, graphical user 14

INVISIBLE 34, 151

invisible 16, 34

ISO 176

J

JPEG 176

JPEG file 19

K

-k 88, 106

-keep 107

L

LAST 142

last 112

LEFT 24, 41, 133, 135, 137, 156, 158

length of text 17

line break 134

line spacing 134

line width, frame 36

M

-ma 74, 108

mark, stamp 72, 119

mirrored 46

MOD 142

multiline 17, 43

N

NEVER 157

no stamp 48

NONE 159

-nopdfa 109

NOT_ROTATE 143, 158

number of stamps 15

O

-o 110
OCR 34
ODD 142
odd 112
-off 83, 111
OPAQUE 32, 138
opaque 16, 27
OPTIONAL_OUTSIDE 157
OUT 159
output file 110
OUTSIDE 157

P

-p 70, 112
page comparison
 tolerance 75
page configuration file 84, 85, 105
page number 67, 118
 change 69
pages
 from stamp template 114
 related to set collation 58
 to be stamped 39, 70, 84, 85, 112
parameter for pdfstamp/pdfstamphft 91
PDF 153, 176
PDF annotation 108
 property 74, 94
 stamp 74
PDF collection 115, 175
PDF configuration file 14, 63, 97, 149
PDF portfolio 175
PDF Tools 20
PDF_DATE_FORMAT 67
PDF_GRAYSTAMP 28, 29, 30, 139
PDF.Author 150
PDF.color_available 150, 152
PDF.colour 150
PDF.compression 150
PDF.Creator 151
PDF.font 34, 151
PDF.gray_available 152
PDF.Keywords 152
PDF.precision 152
PDF.Producer 152
PDF.resolution 152
PDF.Subject 153
PDF.Titel 153
PDF.type 153
PDF.Version 153
PDF/A 71, 99, 109, 176
 conformance level 87

stamp template 87
PDFA 153
pdfstamp 7, 62
 flagpage 76
 parameter 91
 requirement 20
 stamp layout file 21
 stamp text 17
 variable in stamp text 67
pdfstamphft 14, 115
 see also pdfstamp 7
PLOSSYS netdome 7, 175
 flagpage 61
 rotate stamp 55
 scale stamp 55
 stamp 47, 48
 stamp layout file 21
 stamp text 17
plossys.cfg 49, 50, 155
 information 47

PLOT 142
PLS_DIFBACKSTP 57
PLS_ONLYFIRSTSTP 56
PLS_PDF_TOLERANCE_IN_MM 75
PLS_STAMP_MAX 15
PLS_STAMP_n 51, 53, 65
PLS_STAMP_PAGE 84, 105
PNG 176
-pos 83, 113
position, stamp template 83, 113
program for stamping 14
-pst 84, 114

Q

quotes 53

R

-rec 115
recursively, stamp 115
repairing, automatic 14
repeat stamp 44
requirement
 pdfstamp 20
 Unicode 18
reuse temporary stamp file 75
RGB 176
RIGHT 24, 41, 133, 135, 137, 156, 158
ROTATE 143, 158
rotate 38
rotation 55

S

SCALE_STAMP 55, 132
 scaling 55
 SEAL_DEFAULTCODEPAGE 18
 SEALFONTS 18
 SEALRESOURCEPATH 71
 SEALSTAMP 72
 SET 142
 set collation, page number 58
 -setimagemask 116
 -setuu 117
 simulated 30, 102
 SIZE_DEFINITIONS 78, 145
 spacing 46
 special character 53
 srgb.icc 71, 87
 STAMP 27, 139
 stamp 16, 175
 background 32
 delete 73, 95
 delete Adobe 96
 for all output queues 49
 format-specific 78
 gray-simulated 16, 30
 invisible 16, 34
 job-specific 51
 mark 72, 119
 missing 48
 only first page 56
 opaque 16, 27
 page range 39, 70, 84, 85, 112
 pdfstamp 62
 via stamp template 80
 PLOSSYS netdome 48
 program 14
 queue-specific 50
 recursively 115
 reference point 24
 repeat 44
 rotation 55
 scaling 55
 stamp template 80
 TIFF 15
 transparent colored 16, 28
 transparent gray 16, 29
 stamp configuration 14
 Stamp Editor 14
 stamp for front and back side 57
 stamp layout file 21, 63, 120, 130
 back side 57
 examples 161
 template 130

stamp number 15
 stamp template 14, 80
 distance 111
 generate 81
 height 128
 page configuration file 84, 85
 pages from 114
 PDF/A 87
 position 83, 113
 replace text 88
 watermark 86
 width 127
 Stamp text 122
 stamp text
 alignment 41
 character width 46
 default 40
 group 43
 header 53
 mirrored 46
 multiline 17, 43
 pdfstamp 17
 PLOSSYS netdome 17
 spacing 46
 special character 53
 specify directly 66
 starting point 41
 Unicode 18
 variable 17, 67
 variable, PLOSSYS netdome 54
 via header 65
 via stamp text file 64
 stamp text file 64, 124
 stamp type 16
 STAMP_DEFINITION 22, 23, 132
 stamp.rotate 38
 starting point of stamp text 41
 -startpagecount 69, 118
 -sti 72, 119
 -stp 63, 120
 STPFILE 50
 STROKE 151

T

-t 88, 121
 temporary stamp file
 delete 107
 reuse 75
 text
 replace in stamp template 88
 to be replaced 106, 121
 text stamp, configure 22

TEXT_DEFINITIONS 22, 132
TIFF 15, 176
tiffstamp 15
-tn 66, 122
TOLERANCE 78, 131
tolerance for page comparison 75
TOP 24, 41, 133, 137, 158
total page number 67, 123
-totalpagecount 69, 123
TRANSPARENT 32, 138
transparent colored 16, 28, 102
transparent gray 16, 29, 102
TX_ALIGNMENT_HOR 41, 133
TX_ALIGNMENT_VER 41, 133
TX_COLOR 133
TX_EXPANSION 46, 133
TX_FONT 34, 134
TX_LINEBREAK 134
TX_LINEDISTANCE 134
TX_LWSC 135
TX_OFFSETX 42, 135
TX_OFFSETY 42, 135
TX_PATH 135
TX_SIZE 136
TX_SPACING 46, 136
TX_TEXT 40, 136
-txt 64, 124

U

Unicode 18
UP 135
usage 103
-uselogicalpage 125
-usepdfaswatermark 86, 126
UserUnit 117, 175
UTF8 18

V

variable 54
 GKS metafile 60
 in stamp text 17
 pdfstamp 67
VISIBLE_AREA 25, 141

W

WATERMARK 31, 139
watermark 16, 31, 126, 175
 stamp template 86
width of stamp template 127

X

-x 81, 127