

## PLOSSYS Job Parameter

### System Description

Version 4.9.1/5.6.0

2023-10-27

SEAL Systems

## Copyright

This document and all its parts are protected by copyright. Their use without prior written consent by SEAL Systems is prohibited and subject to prosecution. In particular, this applies to reproduction, translation, microfilming and the storing and processing in electronic systems.

Customers that currently own a valid SEAL Systems software license for the product(s) described within the contents of this document, may freely distribute this documentation in electronic form (i. e. CD/File Server or Intranet) for internal usage only.

All product names mentioned are the registered trademarks of the associated companies.

Copyright 2023

SEAL Systems AG  
Lohmühlweg 4  
D-91341 Röttenbach  
Germany

# Contents

<b>1 Introduction.....</b>	<b>7</b>
Conventions in this Documentation .....	8
Overview of Contents .....	9
<b>Description.....</b>	<b>11</b>
<b>2 Processing in PLOSSYS 4.....</b>	<b>13</b>
Header .....	14
Structure.....	15
Header of a Single Job (Header) .....	16
Header of a Set Collation (Set Header).....	17
Header of a Set Member (Header (Set Member)).....	18
Default Header .....	19
Rules for Setting Job Parameters.....	20
<b>3 Processing in PLOSSYS 5 .....</b>	<b>21</b>
Processing of the Job Parameters .....	22
Database Object .....	24
<b>4 Important Configurations.....</b>	<b>25</b>
Job in a Specific Output Format (P4) .....	26
Job on a Specific Medium (P4, P5).....	27
Job as a Set Collation (P4).....	28
Job with Additional Sheet (P4) .....	29
Job with End Processing (P4, P5) .....	30
Job with Additional Information (P4) .....	31
Output as PDF/A (P4).....	32
Job as E-Mail (P4).....	33
Job and Character Encoding/Unicode (P4, P5) .....	35
Job with Multi-Page Files (P4) .....	36
Job with Password (P4).....	37
<b>Reference.....</b>	<b>39</b>
<b>5 Job Parameters - Reference .....</b>	<b>41</b>
PLS_ACCOUNT_KEY (P4) .....	46
PLS_AUX_ABSENDER (P4).....	47
PLS_AUX_ABTEILUNG (P4) .....	48
PLS_AUX_KOSTENSTELLE (P4) .....	49
PLS_AUX_STANDORT (P4) .....	50
PLS_AUX_TELEFON (P4).....	51
(PLS_)BOOKLET (P4, P5).....	52
PLS_CALL_CONDITIONS (P4).....	53
PLS_CDBAN (P4) .....	54
PLS_CDKUR (P4).....	55
(PLS_)COLLATE (P4, P5) .....	56
PLS_CONVERTER_CFG (P4) .....	57
PLS_COST_TYPE (P4).....	58
(PLS_)COSTCENTER (P4, P5) .....	59
PLS_CREATE_COVER (P4).....	60
PLS_CREATE_TRAILER (P4) .....	61
PLS_CROP (P4) .....	62
PLS_CROP_MARKS (P4) .....	63

PLS_CRYPT (P4) .....	64
PLS_CRYPT_OPTIONS (P4).....	65
(PLS_)DATA_0 (_9) (P4, P5).....	66
PLS_DEBUG (P4).....	67
PLS_DELTYPE (P4) .....	68
PLS_DEPARTMENT (P4).....	69
PLS_DIFBACKSTP (P4).....	70
(PLS_)DUMMY_0 (_9) (P4, P5) .....	71
(PLS_)DUPLEX (P4, P5) .....	72
(PLS_)ENABLE_SECUREPRINT (P4, P5) .....	74
PLS_EXECNODE (P4).....	75
PLS_FIXLW (P4) .....	76
PLS_FLAGPAGE (P4) .....	77
(PLS_)FOLD (P4, P5) .....	78
(PLS_)FOLD_TYPE (P4, P5).....	79
PLS_FORM_STYLE (P4) .....	80
PLS_GATE_OUTPUT (P4) .....	81
PLS_GKS_COLTAB (P4) .....	82
(PLS_)GRAY (P4, P5) .....	83
PLS_GS_TIMEOUT (P4).....	84
PLS_HEADER_TYPE (P4) .....	85
PLS_HOLD (P4) .....	86
(PLS_)INFO_0 (_9) (P4, P5).....	87
PLS_INTERNAL_ID (P4).....	88
PLS_IPP_IGNORE_QUEUE (P4).....	89
PLS_JOB_STAT (P4) .....	90
PLS_JOB_STAT_MSG (P4).....	91
(PLS_)JOBNAME (P5).....	92
PLS_LINEWIDTH (P4).....	93
PLS_MAIL (P4) .....	94
PLS_MAIL_COMPRESS (P4) .....	95
PLS_MAIL_FILENAME (P4) .....	96
PLS_MAIL_MERGE_PDF_MEMBER (P4).....	97
PLS_MAIL_MESSAGE (P4) .....	98
PLS_MAIL_MESSAGE_TEXT_TYPE (P4).....	99
PLS_MAIL_SEND_ATTACHMENT (P4) .....	100
PLS_MAIL_TEXTFILE (P4).....	101
PLS_MAIL_USE_SET_HEADER (P4).....	102
PLS_MAIL_USE_TEXTFILE (P4) .....	103
PLS_MAIL_ZIP (P4) .....	104
PLS_MAIL_ZIP_FILENAME (P4).....	105
PLS_MAIL_ZIP_MEMBER (P4) .....	106
PLS_MARKER (P4) .....	107
PLS_MAXMAILSIZE (P4).....	108
mediaSize (P5).....	109
PLS_META_n (P4).....	110
PLS_META_TYPE (P4) .....	113
PLS_MIRROR (P4).....	114
PLS_NETTO_PLOTSIZE (P4) .....	115
PLS_ONLYFIRSTSTP (P4) .....	116
PLS_ORIG_EXT (P4) .....	117
(PLS_)ORIG_NAME (P4, P5).....	118

PLS_PAGES (P4) .....	119
PLS_PAPER_OPT (P4) .....	120
PLS_PDF_OWNER_PASSWD (P4) .....	121
PLS_PDF_PASSWD (P4) .....	122
PLS_PENTAB (P4) .....	123
PLS_PLOT_FORMAT (P4) .....	124
PLS_PLOT_ROTATE (P4) .....	125
(PLS_)PLOTCOPY (P4, P5) .....	126
PLS_PLOTDATE (P4) .....	127
(PLS_)PLOTID (P4, P5) .....	128
PLS_PLOTITEM (P4) .....	129
(PLS_)PLOT PAPER (P4, P5) .....	130
(PLS_)PLOT PEN (P4, P5) .....	132
PLS_PLOTSCALE (P4) .....	133
PLS_PLOTSIZE (P4) .....	134
(PLS_)PLOTTER (P4, P5) .....	135
(PLS_)PLOTTYPE (P4, P5) .....	136
PLS_POOLPLOTTER_ALL (P4) .....	139
(PLS_)PRINT_QUALITY (P4, P5) .....	140
PLS_PRIO (P4) .....	141
(PLS_)PUNCH (P4, P5) .....	142
(PLS_)PUNCH_TYPE (P4, P5) .....	143
PLS_RECEIVER (P4) .....	144
PLS_RECEIVER_BCC (P4) .....	145
PLS_RECEIVER_CC (P4) .....	146
PLS_ROTATE (P4) .....	147
PLS_SAVE_SPOOLFILE (P4) .....	148
scaleFactor (P5) .....	149
scaleMode (P5) .....	150
PLS_SCALE_TYPE (P4) .....	152
PLS_SCRNODE (P4) .....	154
(PLS_)SECUREPRINT (P4, P5) .....	155
PLS_SENDER (P4) .....	156
PLS_SET_COPY (P4) .....	157
PLS_SET_MEMBER_NAME (P4) .....	158
PLS_SET_NAME (P4) .....	159
PLS_SET_NUMBER (P4) .....	160
(PLS_)SORT (P4, P5) .....	161
(PLS_)SORT_TYPE (P4, P5) .....	162
PLS_SPLITTYPE (P4) .....	164
PLS_SRCAPPL (P4) .....	166
PLS_STAMP_0 (_n) (P4) .....	167
(PLS_)STAPLE (P4, P5) .....	169
(PLS_)STAPLE_TYPE (P4, P5) .....	170
PLS_START_TIME (P4) .....	171
PLS_STATISTIC_0 (_2) (P4) .....	172
PLS_SUBJECT (P4) .....	173
PLS_TEXTLINEWIDTH (P4) .....	174
(PLS_)TRAY_1 (_n) (P4, P5) .....	175
PLS_USEMETA (P4) .....	177
PLS_USERGROUP (P4) .....	178
(PLS_)USERNAME (P4, P5) .....	179

---

PLS_WINDOW (P4).....	180
PLS_WINDOW_PAGENUMBER (P4) .....	181
SEAL_CODEPAGE (P4) .....	182
SEAL_ORIGCODEPAGE (P4) .....	183
<b>Appendix A Supported Character Encodings.....</b>	<b>184</b>
<b>Bibliography.....</b>	<b>185</b>
<b>Terminology.....</b>	<b>186</b>
<b>Abbreviations.....</b>	<b>189</b>
<b>Keywords .....</b>	<b>190</b>
<b>Index.....</b>	<b>193</b>

# 1 Introduction

.....  
 This documentation describes the job parameters of output jobs for PLOSSYS 4 and PLOSSYS 5.  
 .....

purpose

.....  
 In connection with PLOSSYS 5 and in this comprehensive documentation, PLOSSYS 4 is used for PLOSSYS netdome alternatively.  
 .....



hint -  
 PLOSSYS net-  
 dome

.....  
 In general, PLOSSYS 5 supports the same job parameters as PLOSSYS 4. However, due to the reduced functionality, not all job parameters that can be used in PLOSSYS 4 are also supported in PLOSSYS 5.  
 .....

PLOSSYS 4/  
 PLOSSYS 5

.....  
 This documentation is intended for PLOSSYS 4 and PLOSSYS 5 administrators who want to configure the output of jobs.  
 .....

target group

.....  
 This chapter deals with the following topics:  
 .....

in this chapter

Topic	Page
Conventions in this Documentation	8
Overview of Contents	9

.....

## Conventions in this Documentation

path specifica-  
tion

.....

The path information given in this documentation is relative to the installation directory of PLOSSYS 4. This is usually the home directory of the `plossys` user with PLOSSYS 4. The path information is indicated in Windows notation only in most cases. This corresponds to the UNIX directory structures unless noted otherwise.

.....

typography

.....

The following table lists the typographical conventions employed in this documentation.

Typographical Convention	Meaning
Consolas	File names, paths, commands, menu items, keywords, special values, short scripts and examples
<i>Consolas italic</i>	Parameters; variables that have to be replaced by current values
Consolas <small></small>	More extensive scripts and examples

.....



## Overview of Contents

.....  
 This documentation has two parts: a description and a reference. The first part describes the functionality and the installation process using figures, step-by-step-procedures and explanatory texts. The second part serves as a detailed reference guide, containing configuration settings, keywords etcetera.

structure

.....  
 The description deals with the following topics:

description

*Processing in PLOSSYS 5*, page 21, describes the headers in which the job parameters are passed to PLOSSYS 4.

*Processing in PLOSSYS 5*, page 21, explains how the job parameters are transferred to PLOSSYS 5.

*Important Configurations*, page 25, describes the most common configuration options that are relevant for job parameters.

.....  
 The reference contains the following chapters:

reference

- *Job Parameters - Reference*, page 41, with a listing of all job parameters for PLOSSYS 4 and/or PLOSSYS 5 and their value ranges.


.....  
 Appendix A contains a list of supported character encodings.

appendix

.....  
 At the end of the documentation, a bibliography, terminology list, abbreviation list, and index are included.

directories





**Description**



## 2 Processing in PLOSSYS 4

---

.....  
This chapter deals with the following topics:

in this chapter

<b>Topic</b>	<b>Page</b>
Header	14
Structure	15
Header of a Single Job (Header)	16
Header of a Set Collation (Set Header)	17
Header of a Set Member (Header (Set Member))	18
Important Configurations	25
Rules for Setting Job Parameters	20

---

## Header

purpose	<p>.....</p> <p>A header controls the processing and the output of a job in PLOSSYS 4.</p> <p>A header is a configuration file which contains the following information (job parameters):</p> <ul style="list-style-type: none"> <li>• job parameters for the processing of the job</li> <li>• job parameters for the output of the job</li> <li>• information about the job</li> </ul> <p>.....</p>
for each job	<p>.....</p> <p>Each job has to have a header.</p> <p>.....</p>
names	<p>.....</p> <p>A header has the name of the correspondent job and the .hed file extension.</p> <p>.....</p>
storage	<p>.....</p> <p>The header is located parallel to the job.</p> <p>.....</p>
creation	<p>.....</p> <p>Normally, the header is created by the PLOSSYS 4 clients.</p> <p>.....</p>
default	<p>.....</p> <p>There is a default for each job parameter.</p> <p>The required job parameters are set by the conversion service or the defaults are taken.</p> <p>.....</p>
configuration	<p>.....</p> <p>The header can be configured via the following user interfaces:</p> <ul style="list-style-type: none"> <li>• PLOSSYS netdome Settings (PNE)             <ul style="list-style-type: none"> <li>→ [NETDOME_SETTINGS_TEC]</li> </ul> </li> </ul> <p>.....</p>


## Structure

.....  
A header has the following structure:

structure

- Headers are sequential ASCII files.
- One job parameter with keyword and value is specified per line.
  - `$jobparameter == „value“`
  - The job parameter starts with \$ (dollar sign).
  - The value has to be enclosed in "" (double quotation marks).
- Settings within the value are separated by blanks.

.....  
The PLS\_PLOTSIZE job parameter specifies the output format of the job. The output format is DIN A4 portrait:

 example

- `$PLS_PLOTSIZE == 0.000000 0.000000 0.209900 0.297040`
- .....

## Header of a Single Job (Header)

sign

A header is specified by the following job parameter:

```
$PLS_HEADER_TYPE == PLOT
```

mandatory parameter

The header of a single job has the following mandatory parameters:

Job Parameter	Description
PLS_HEADER_TYPE	job type
PLS_PLOTTYPE	output type
PLS_SRCNODE	source server
PLS_USERNAME	user name
PLS_PLOTTER	output device
PLS_PLOTID	ID of the single job
PLS_PLOTSIZE	output format



hint -  
PLS\_PLOTSIZE

The output format, PLS\_PLOTSIZE, is determined by the format converter during the preprocessing and is written into the header.



example

extract of a job header:

```

pl000010.h00 + (T:\ae) - GVIM
Datei Editieren Werkzeuge Syntax Puffer Ansicht Hilfe
$ PLS_HEADER_TYPE == "PLOT"
$ PLS_SRCNODE == "pls_node"
$ PLS_USERNAME == "anja"
$ PLS_PLOTID == "Kandinsky I"
$ PLS_INTERNAL_ID == "UNDEFINED"
$ PLS_PLOTTYPE == "PDF"
$ PLS_PLOTSIZE == "0.000000 0.000000 0.129470 0.157340"
$ PLS_PLOTSCALE == "2.0"
$ PLS_PLOTPAPER == "BE"
$ PLS_PLOTPEN == "BE"
$ PLS_PLOTCOPY == "0"

```



related topics

→ *Job Parameters - Reference*, page 41



## Header of a Set Collation (Set Header)

The set header is specified by the following job parameter:

```
$PLS_HEADER_TYPE == SET_COLLATION
```

sign


A set header has the following mandatory parameters:

mandatory parameter

Set Header Parameters	Description
PLS_HEADER_TYPE	header type
PLS_SRCNODE	source server
PLS_USERNAME	user name
PLS_PLOTTER	output device
PLS_SET_NAME	name of the set collation
PLS_SET_NUMBER	number of set members
PLS_SET_MEMBER_NAME	names of the set members

extract of a set header:

 example




```

$ PLS_HEADER_TYPE == "SET_COLLATION"
$ PLS_PAGECOUNT == "4"
$ PLS_PLOTID == "Testsatz"
$ PLS_PLOTPAPER == "BE"
$ PLS_PLOTPEN == "BE"
$ PLS_PLOTTER == "Testdrucker"
$ PLS_SET_COPY == "0"
$ PLS_SET_MEMBER_NAME == "Kandinsky I"
$ PLS_SET_MEMBER_NAME == "Capitol"
$ PLS_SET_MEMBER_NAME == "Formattabelle PDF"
$ PLS_SET_NAME == "Testsatz"
$ PLS SET NUMBER == "3"

```

→ *Job Parameters - Reference*, page 41

 related topics

## Header of a Set Member (Header (Set Member))

set member


A header (set member) is specified by the following job parameter:

```
$PLS_HEADER_TYPE == PLOT
$PLS_SET_NAME == Name_SetCollation
```


mandatory parameter

A set member has the following mandatory parameters:


Job Parameter	Description
PLS_PLOTTYPE	output type
PLS_SRCNODE	source server
PLS_USERNAME	user name
PLS_PLOTTER	output device
PLS_PLOTID	ID of the set member
PLS_PLOTSIZE	output format
PLS_SET_NAME	name of the set collation

 example

extract of a set member header:



```
pl000016.h00 + (T:\ae) - GVIM
Datei Editieren Werkzeuge Syntax Puffer Ansicht Hilfe
$ PLS_HEADER_TYPE == "PLOT"
$ PLS_SRCNODE == "plossys"
$ PLS_USERNAME == "anja"
$ PLS_EXECPNODE == "UNDEFINED"
$ PLS_PLOTTER == "Testdrucker"
$ PLS_PLOTID == "TIFF DIN A4 hoch"
$ PLS_INTERNAL_ID == "UNDEFINED"
$ PLS_PLOTTYPE == "PDF"
$ PLS_PLOTSIZE == "0.000000 0.000000 0.209900 0.297040"
$ PLS_PLOTSCALE == "1.0"
$ PLS_SET_NAME == "Testsatz"
$ PEGASUS_JOBNO == "16"
$ PLS_FOLLOW_ME == "N"
```

 related topics

→ *Job Parameters - Reference*, page 41

## Default Header

.....  
PLOSSYS 4 provides the possibility to specify job parameters as default job parameters for a graphic format.  
.....

default job parameter

You have the following possibilities:

- specify the job parameter in the default header of the client
- specify the job parameter for a graphic format within the conversion service  
→ [NETDOME\_SETTINGS\_TEC]
- specify the job parameter for a graphic format in the correspondent format converter or gate  
server\plotserv\gates\*gatename*\default.hed



**Caution** - restricted support:

As of PLOSSYS 4 version 4.4.0, the gate method is replaced by the conversion service.  
.....

## Rules for Setting Job Parameters

---

.....  
PLOSSYS 4 sets job parameters according to the following rules:

- Headers created by the client application or the CAD system and sent to PLOSSYS 4 together with the graphic file overwrite the settings in the default headers.
  - PLOSSYS 4 also evaluates values sent via PostScript comments or via the IPP collection `seal-attributes`, → *Processing of the Job Parameters*, page 22.
  - Transmitted headers are complimented with job parameters of the default header.
  - Job parameters which are complemented, are appended at the end of the header.
  - If a job parameter is set more than once, the value set last is valid.
  - Internal PLOSSYS 4 processes modify and compliment the header (→ *PLS\_PLOTSIZE (P4)*, page 134).
- .....

### 3 Processing in PLOSSYS 5

.....

This chapter deals with the following topics:

in this chapter

Topic	Page
Processing of the Job Parameters	22
Database Object	24

.....

## Processing of the Job Parameters

transfer

Job parameters can be passed to PLOSSYS 5 in the following ways:

- Comments in the transferred PostScript file
- IPP collection seal-attributes

PostScript  
comment

In a PostScript file created by SEAL MasterDriver, job parameters can be transferred to PLOSSYS 5 in the form of PostScript comments. % marks a comment in PostScript. The quotation marks around the value ("`<value>`") are being replaced by exclamation marks (!`<value>`!).



example

```
%%PLSHED: $ PLS_DUPLEX == !LONG_SIDE!
```

IPP collection

When using IPP transfer, job parameters can be sent to PLOSSYS 5 within the IPP collection seal-attributes.

send2pls

The send2pls program by SEAL Systems can create the IPP collection seal-attributes when transferring jobs to PLOSSYS 5 via IPP. To do so, you can add the -param parameter when calling send2pls or send a header file with send2pls.

IPP or LPR  
parameters

PLOSSYS 5 can use some parameters of the transfer protocols (IPP or LPR) that are being used to send the job to PLOSSYS 5, for example job and user names.

→ *Job Parameters - Reference, page 41*

priority

The job parameters are evaluated in the following order:

- PostScript file (highest priority)
- IPP collection seal-attributes
- LPR attribute
- default IPP attribute



reference

You find the mapping of some job parameters and their priority depending on their origin in the PLOSSYS 5 documentation, too:

→ [https://plossys-5.docs.sealsystems.de/reference/ipp\\_attribute\\_mapping.html](https://plossys-5.docs.sealsystems.de/reference/ipp_attribute_mapping.html)


..... *To be continued*

## Processing of the Job Parameters, Continuation

.....  
During the evaluation of the job parameters, PLOSSYS 5 will remove the PLS\_ prefix if it exists. The name of job parameters without this prefix stays the same.  
.....

without PLS\_ prefix


.....  
PLS\_DUPLEX becomes DUPLEX.  
.....

 example

## Database Object

output job

For PLOSSYS 5, the job parameters will be added to the database object of the output job.

 example


For an example of a database object, refer to the PLOSSYS 5 documentation:  
→ [https://plossys-5.docs.sealsystems.de/reference/db\\_object\\_examples/db\\_object\\_example\\_job.html](https://plossys-5.docs.sealsystems.de/reference/db_object_examples/db_object_example_job.html)

job.orig

job.orig contains the job parameters set at the time of the job input.

job.current

job.current contains the currently valid job parameters. These could have been changed by customer-specific processes.

 example

For example, job.current.DUPLEX contains the currently effective value of the DUPLEX job parameter. It can be changed, for example, in customer-specific processes during the preprocessing.

 hint - printer driver template

The structure of the job parameters in the printer driver templates is different from the structure of the database object. In the printer driver templates, all job parameters from the job.current database object are listed directly in job. There are also additional structures, like job.page and job.low, that cannot be used with PLOSSYS 5.



## 4 Important Configurations

The following chapter deals with the most important configuration possibilities which can be performed by PLOSSYS 4 and PLOSSYS 5 job parameters.

introduction

According to the tasks, the headers relevant for the configuration are listed.

For further information about the single job parameters, refer to the Reference.

 reference

This chapter deals with the following topics:

in this chapter

Topic	Page
Job in a Specific Output Format (P4)	26
Job on a Specific Medium (P4, P5)	27
Job as a Set Collation (P4)	26
Job with Additional Sheet (P4)	29
Job with End Processing (P4, P5)	30
Job with Additional Information (P4)	31
Output as PDF/A (P4)	31
Job as E-Mail (P4)	33
Job and Character Encoding/Unicode (P4, P5)	35
Job with Multi-Page Files (P4)	36
Job with Password (P4)	37

## Job in a Specific Output Format (P4)

purpose	<p>.....</p> <p>PLOSSYS 4 offers the possibility to control the format of a job via job parameters.</p> <p>.....</p>
format specifications	<p>.....</p> <p>PLOSSYS 4 distinguishes between the following possibilities to control the format of a job:</p> <ul style="list-style-type: none"> <li>• Scaling           <ul style="list-style-type: none"> <li>• System-internal scaling types (PLS_SCALE_TYPE)</li> <li>• Configurable scaling rules (PLS_PLOT_SCALE)</li> </ul> </li> <li>• Rotation</li> <li>• Splitting</li> <li>• Line width</li> </ul> <p>.....</p>
relevant job parameters	<p>.....</p> <p>In this context, the following job parameters are relevant:</p> <p>→ <i>PLS_LINEWIDTH (P4)</i>, page 93 (line width for vectors)</p> <p>→ <i>PLS_MIRROR (P4)</i>, page 114 (mirroring)</p> <p>→ <i>PLS_PLOT_ROTATE (P4)</i>, page 125 (rotation)</p> <p>→ <i>PLS_PLOTSCALE (P4)</i>, page 133 (scaling factor)</p> <p>→ <i>PLS_PLOTSIZE (P4)</i>, page 134 (output format)</p> <p>→ <i>PLS_ROTATE (P4)</i>, page 147 (rotation for HPGL files)</p> <p>→ <i>PLS_SCALE_TYPE (P4)</i>, page 152 (scaling type)</p> <p>→ <i>PLS_SPLITTYPE (P4)</i>, page 164 (splitting)</p> <p>.....</p>

## Job on a Specific Medium (P4, P5)

PLOSSYS 4 and PLOSSYS 5 offers the possibility to control the output medium of a job via job parameters.

purpose

Depending on how `*PAPER_SELECT*` is set on the output device, PLOSSYS 4 behaves differently:

behavior in PLOSSYS 4

- `PAPERSIZE: (PLS_)PLOT PAPER` will be ignored.



hint - operation request

The job hangs with an operation request in PLOSSYS 4 if no tray has been assigned to this paper size, unless `ASK_PAPER` is set to `N` with the queue.

- `DRAWER`: PLOSSYS 4 selects the first appropriate tray based on the tray settings (paper size and paper type). The tray number is transferred to the output device.
- `MEDIA`: The media type is transferred to the output device ( $\rightarrow$  `(PLS_)PLOT PAPER (P4, P5)`, page 130). On the output device, the media type has to be set directly for one of the trays (not in PLOSSYS 4), otherwise the output device will stop and request the appropriate media.



hint - manufacturer-dependent

Not all manufacturers support all of our standard media. If necessary, similar media types are used or, if nothing suitable is available, mapped to plain paper (`PLAIN`).

- `PAPER_SELECT AUTO`: Media can also be set in `(PLS_)TRAY_n`. If a tray number (`INTRAYx`) is set in `(PLS_)TRAY_n`, the tray number is passed to the output device. If a media type is set in `(PLS_)TRAY_n`, the media type is passed to the output device.

Media can be set in `(PLS_)TRAY_n`. If a tray number (`INTRAYx`) is set in `(PLS_)TRAY_n`, the tray number is passed to the output device. If a media type is set in `(PLS_)TRAY_n`, the media type is passed to the output device (as with PLOSSYS 4 with `PAPER_SELECT AUTO`). Additionally, PLOSSYS 5 supports `(PLS_)PLOT PAPER`.

behavior in PLOSSYS 5

In this context, the following job parameters are relevant:

relevant job parameters

$\rightarrow$  `(PLS_)PLOT PAPER (P4, P5)`, page 130 (output medium)

$\rightarrow$  `(PLS_)TRAY_1 (_n) (P4, P5)`, page 175 (output tray)

The `FALLBACK_xx` keyword in `plossys.cfg` specifies an alternative output medium if the original output medium is not available.

alternative output medium

Unless the alternative output medium is available, an operation request is displayed for this output device.

## Job as a Set Collation (P4)

purpose

.....  
PLOSSYS 4 offers the possibility to collect output jobs to set collations and to output them as one package.

→ *Header of a Set Collation (Set Header)*, page 17  
.....

relevant

job parameters

.....  
In this context, the following job parameters are relevant:

→ *PLS\_SET\_COPY (P4)*, page 157 (numbers of copies)

→ *PLS\_SET\_NAME (P4)*, page 159 (set name)

→ *PLS\_SET\_MEMBER\_NAME (P4)*, page 158 (name of the set member)

→ *PLS\_SET\_NUMBER (P4)*, page 160 (number of single jobs)  
.....

## Job with Additional Sheet (P4)

.....  
PLOSSYS 4 offers the possibility to control the creation of additional sheets for output jobs via job parameters. purpose  
.....

PLOSSYS 4 distinguishes between the following types of additional sheets: additional sheets

- Cover sheet
- Trailer sheet
- Error sheet
- Missing sheet (for redirected documents with a pool device)
- Missing sheet (for missing documents in a set collation)

For further information about the configuration of the layout of the additional sheets for example, refer to:



→ [NETDOME\_ADDSH\_TEC]

.....  
In this context, the following job parameters are relevant: relevant  
job parameters

→ *PLS\_CREATE\_COVER (P4)*, page 60 (cover sheet)

→ *PLS\_CREATE\_TRAILER (P4)*, page 61 (trailer sheet)

→ *PLS\_FORM\_STYLE (P4)*, page 80 (layout)

→ *PLS\_META\_TYPE (P4)*, page 113 (document type)  
.....

## Job with End Processing (P4, P5)

purpose	<p>.....</p> <p>PLOSSYS 4 offers the possibility to control the end processing of a job via job parameters.</p> <p>.....</p>
end processing	<p>.....</p> <p>PLOSSYS 4 distinguishes between the following possibilities of the end processing:</p> <ul style="list-style-type: none"> <li>• Booklet output</li> <li>• Fold</li> <li>• Staple</li> <li>• Punch</li> <li>• Sort</li> </ul> <p>.....</p>
relevant job parameters	<p>.....</p> <p>In this context, the following job parameters are relevant:</p> <p>→ <i>(PLS_)BOOKLET (P4, P5)</i>, page 52 (booklet output)</p> <p>→ <i>(PLS_)FOLD (P4, P5)</i>, page 78 (folding)</p> <p>→ <i>(PLS_)FOLD_TYPE (P4, P5)</i>, page 79 (fold type)</p> <p>→ <i>(PLS_)STAPLE (P4, P5)</i>, page 169 (staple)</p> <p>→ <i>(PLS_)STAPLE_TYPE (P4, P5)</i>, page 170 (staple type)</p> <p>→ <i>(PLS_)PUNCH (P4, P5)</i>, page 142 (punching)</p> <p>→ <i>(PLS_)PUNCH_TYPE (P4, P5)</i>, page 143 (punch type)</p> <p>→ <i>(PLS_)SORT (P4, P5)</i>, page 161 (sorting)</p> <p>→ <i>(PLS_)SORT_TYPE (P4, P5)</i>, page 162 (sort type)</p> <p>.....</p>

## Job with Additional Information (P4)

.....

PLOSSYS 4 offers the possibility to add additional information, for instance distribution information or stamps, via job parameters to a job. purpose

.....

PLOSSYS 4 distinguishes between the following additional information types: additional information

- Cost center
  - Location
  - Telephone
  - Sender
  - Receiver
  - Department ID
  - Label
  - Special field
  - Messenger office
  - Stamp
  - Console type
  - Company-specific (any) information
- .....

In this context, the following job parameters are relevant: relevant job parameters

- *PLS\_ACCOUNT\_KEY (P4)*, page 46 (cost center)
  - *PLS\_AUX\_ABSENDER (P4)*, page 47 (sender)
  - *PLS\_AUX\_ABTEILUNG (P4)*, page 48 (department)
  - *PLS\_AUX\_KOSTENSTELLE (P4)*, page 49 (cost center)
  - *PLS\_AUX\_STANDORT (P4)*, page 50 (location)
  - *PLS\_AUX\_TELEFON (P4)*, page 51 (telephone)
  - *PLS\_CDBAN (P4)*, page 54 (initials or department)
  - *PLS\_CDKUR (P4)*, page 55 (messenger office)
  - *PLS\_COST\_TYPE (P4)*, page 58 (console type)
  - *(PLS\_)DATA\_0 (\_9) (P4, P5)*, page 66 (company-specific information)
  - *PLS\_DEPARTMENT (P4)*, page 69 (department)
  - *(PLS\_)DUMMY\_0 (\_9) (P4, P5)*, page 71 (company-specific information)
  - *PLS\_RECEIVER (P4)*, page 144 (receiver)
  - *PLS\_STAMP\_0 (\_n) (P4)*, page 167 (stamp)
- .....

## Output as PDF/A (P4)

purpose	<p>.....</p> <p>PLOSSYS 4 offers the possibility to create PDF or PDF/A files and to add meta-data to these files.</p> <p>.....</p>
restriction	<p>.....</p> <p>The following restrictions apply to the PDF/A processing:</p> <ul style="list-style-type: none"> <li>• Creating PDF/A is not possible when output a job via e-mail.</li> </ul> <p>.....</p>
configuration options	<p>.....</p> <p>PLOSSYS 4 offers the following possibilities to configure the output of PDF or PDF/A files:</p> <ul style="list-style-type: none"> <li>• Specifying metadata</li> <li>• Setting metadata</li> <li>• Encoding (only with MAIL output type)</li> <li>• Setting password</li> </ul> <p>.....</p>
relevant job parameters	<p>.....</p> <p>In this context, the following job parameters are relevant:</p> <p>→ <i>PLS_USEMETA (P4)</i>, page 177 (setting metadata)</p> <p>→ <i>PLS_META_n (P4)</i>, page 110 (metadata)</p> <p>→ <i>PLS_CRYPT (P4)</i>, page 64 (encoding)</p> <p>→ <i>PLS_CRYPT_OPTIONS (P4)</i>, page 65 (encoding options)</p> <p>→ <i>PLS_PDF_PASSWD (P4)</i>, page 122 (user password)</p> <p>→ <i>PLS_PDF_OWNER_PASSWD (P4)</i>, page 121 (owner password)</p> <p>.....</p>



## Job as E-Mail (P4)

.....  
 PLOSSYS 4 offers the possibility to output a single job or a set collation as e-mail. purpose

.....  
 PLOSSYS 4 offers the following possibilities to configure the output of a job as an e-mail via job parameters:

- Receiver configuration options
- Sender
- Subject
- Message field
- Text format
- Attachment
- Compressing
- Encoding
- Maximum size of the e-mail file

.....  
 In this context, the following job parameters are relevant: relevant job parameters, part 1

→ *PLS\_CRYPT (P4)*, page 64 (encoding)

→ *PLS\_CRYPT\_OPTIONS (P4)*, page 65 (encoding options)

→ *PLS\_MAIL (P4)*, page 94 (job as e-mail)

→ *PLS\_MAIL\_COMPRESS (P4)*, page 95 (compressing)

→ *PLS\_MAIL\_FILENAME (P4)*, page 96 (name of the attachment)

→ *PLS\_MAIL\_MESSAGE (P4)*, page 98 (message field)

→ *PLS\_MAIL\_TEXTFILE (P4)*, page 101 (text format)

→ *PLS\_MAIL\_MERGE\_PDF\_MEMBER (P4)*, page 97 (assembling set members)

..... *To be continued*

## Job as E-Mail (P4), Continuation

relevant job parameters, part 2

- *PLS\_MAIL\_SEND\_ATTACHMENT (P4)*, page 100 (text or attachment)
- *PLS\_MAIL\_USE\_TEXTFILE (P4)*, page 103 (text file for message field)
- *PLS\_MAIL\_USE\_SET\_HEADER (P4)*, page 102 (header priorities)
- *PLS\_MAIL\_ZIP (P4)*, page 104 (compressing)
- *PLS\_MAIL\_ZIP\_FILENAME (P4)*, page 105 (name of the ZIP file)
- *PLS\_MAIL\_ZIP\_MEMBER (P4)*, page 106 (set member in ZIP file)
- *PLS\_MAXMAILSIZE (P4)*, page 108 (maximum size)
- *PLS\_RECEIVER (P4)*, page 144 (receiver)
- *PLS\_RECEIVER\_CC (P4)*, page 146 (additional receiver)
- *PLS\_RECEIVER\_BCC (P4)*, page 145 (additional receiver)
- *PLS\_SENDER (P4)*, page 156 (sender)
- *PLS\_SUBJECT (P4)*, page 173 (subject)

## Job and Character Encoding/Unicode (P4, P5)

.....  
PLOSSYS 4 offers the possibility to process a job in different character encodings.

purpose

PLOSSYS 5 processes UTF-8 only.

.....  
In this context, the following job parameters are relevant:

relevant job parameters

→ *SEAL\_CODEPAGE (P4)*, page 182 (character encoding)

→ *SEAL\_ORIGCODEPAGE (P4)*, page 183 (original encoding)

## Job with Multi-Page Files (P4)

### purpose

PLOSSYS 4 offers the possibility to configure the output of multi-page files via job parameters.

### configuration options

PLOSSYS 4 offers the following configuration possibilities:

- Duplex printing
- Partial window for output
- Page specification
- Stamp

### relevant job parameters

In this context, the following job parameters are relevant:

- *(PLS\_)DUPLEX (P4, P5)*, page 72 (duplex printing)
- *PLS\_PAGES (P4)*, page 119 (page specification for output)
- *PLS\_ONLYFIRSTSTP (P4)*, page 116 (stamping)
- *PLS\_DIFBACKSTP (P4)*, page 70 (stamping)
- *PLS\_WINDOW\_PAGENUMBER (P4)*, page 181 (cropped window)

### relevant keywords

In this context, the following keywords in `plossys.cfg` are relevant:



### reference

- *DUPLEX\_GENERATE*, [NETDOME\_TEC]

## Job with Password (P4)


.....  
 PLOSSYS 4 provides the possibility to secure the output of single jobs using a password. In order to output the job, the user has to enter the password at the printer directly.

purpose

.....  
 You set the password in the PLS\_SECUREPRINT job parameter. Via the PLS\_ENABLE\_SECUREPRINT job parameter, you can also control if the password is to be used at all when a password has been set.

configuration

.....  
 The rules which apply for the password, for example, if only digits are allowed or the maximal length of the password, depend on the specific output device!

 hint - printer-dependent

.....  
 In PLOSSYS OCON, the PLS\_SECUREPRINT job parameter is not displayed as clear text but with placeholder characters.

PLOSSYS OCON

.....  
 In this context, the following job parameters are relevant:


relevant job parameters

→ (PLS\_)ENABLE\_SECUREPRINT (P4, P5), page 74 (Evaluation of the password)

→ (PLS\_)SECUREPRINT (P4, P5), page 155 (Password for the output)

.....





**Reference**





## 5 Job Parameters - Reference

The title of each job parameter shows, if it is applicable for PLOSSYS 4 (P4) and/or PLOSSYS 5 (P5).

PLOSSYS 4/  
PLOSSYS 5

This chapter describes the following job parameters:

in this chapter

Topic	Page
PLS_ACCOUNT_KEY (P4)	46
PLS_AUX_ABSENDER (P4)	47
PLS_AUX_ABTEILUNG (P4)	48
PLS_AUX_KOSTENSTELLE (P4)	49
PLS_AUX_STANDORT (P4)	50
PLS_AUX_TELEFON (P4)	51
(PLS_)BOOKLET (P4, P5)	52
PLS_CALL_CONDITIONS (P4)	53
PLS_CDBAN (P4)	54
PLS_CDKUR (P4)	55
(PLS_)COLLATE (P4, P5)	56
PLS_CONVERTER_CFG (P4)	57
PLS_COST_TYPE (P4)	58
(PLS_)COSTCENTER (P4, P5)	59
PLS_CREATE_COVER (P4)	60
PLS_CREATE_TRAILER (P4)	61
PLS_CROP (P4)	62
PLS_CROP_MARKS (P4)	63
PLS_CRYPT (P4)	64
PLS_CRYPT_OPTIONS (P4)	65
(PLS_)DATA_0 (_9) (P4, P5)	66
PLS_DEBUG (P4)	67
PLS_DELTYPE (P4)	68
PLS_DEPARTMENT (P4)	69
PLS_DIFBACKSTP (P4)	70
(PLS_)DUMMY_0 (_9) (P4, P5)	71

Topic	Page
(PLS_)DUPLEX (P4, P5)	72
(PLS_)ENABLE_SECUREPRINT (P4, P5)	74
PLS_EXECNODE (P4)	75
PLS_FIXLW (P4)	76
PLS_FLAGPAGE (P4)	77
(PLS_)FOLD (P4, P5)	78
(PLS_)FOLD_TYPE (P4, P5)	79
PLS_FORM_STYLE (P4)	80
PLS_GATE_OUTPUT (P4)	81
PLS_GKS_COLTAB (P4)	82
(PLS_)GRAY (P4, P5)	83
PLS_GS_TIMEOUT (P4)	84
PLS_HEADER_TYPE (P4)	85
PLS_HOLD (P4)	86
(PLS_)INFO_0 (_9) (P4, P5)	87
PLS_INTERNAL_ID (P4)	88
PLS_IPP_IGNORE_QUEUE (P4)	89
PLS_JOB_STAT (P4)	90
PLS_JOB_STAT_MSG (P4)	91
(PLS_)JOBNAME (P5)	92
PLS_LINEWIDTH (P4)	93
PLS_MAIL (P4)	94
PLS_MAIL_COMPRESS (P4)	95
PLS_MAIL_FILENAME (P4)	96
PLS_MAIL_MERGE_PDF_MEMBER (P4)	97
PLS_MAIL_MESSAGE (P4)	98
PLS_MAIL_MESSAGE_TEXT_TYPE (P4)	99
PLS_MAIL_SEND_ATTACHMENT (P4)	100
PLS_MAIL_TEXTFILE (P4)	101
PLS_MAIL_USE_SET_HEADER (P4)	102
PLS_MAIL_USE_TEXTFILE (P4)	103
PLS_MAIL_ZIP (P4)	104

Topic	Page
PLS_MAIL_ZIP_FILENAME (P4)	105
PLS_MAIL_ZIP_MEMBER (P4)	106
PLS_MARKER (P4)	107
PLS_MAXMAILSIZE (P4)	108
mediaSize (P5)	109
PLS_META_n (P4)	110
PLS_META_TYPE (P4)	113
PLS_MIRROR (P4)	114
PLS_NETTO_PLOTSIZE (P4)	115
PLS_ONLYFIRSTSTP (P4)	116
PLS_ORIG_EXT (P4)	117
(PLS_)ORIG_NAME (P4, P5)	118
PLS_PAGES (P4)	119
PLS_PAPER_OPT (P4)	120
PLS_PDF_OWNER_PASSWD (P4)	121
PLS_PDF_PASSWD (P4)	122
PLS_PENTAB (P4)	123
PLS_PLOT_FORMAT (P4)	124
PLS_PLOT_ROTATE (P4)	125
(PLS_)PLOTCOPY (P4, P5)	126
PLS_PLOTDATE (P4)	127
(PLS_)PLOTID (P4, P5)	128
PLS_PLOTITEM (P4)	129
(PLS_)PLOT PAPER (P4, P5)	130
(PLS_)PLOT PEN (P4, P5)	132
PLS_PLOTSCALE (P4)	133
PLS_PLOTSIZE (P4)	134
(PLS_)PLOTTER (P4, P5)	135
(PLS_)PLOTTYPE (P4, P5)	136
PLS_POOLPLOTTER_ALL (P4)	139
(PLS_)PRINT_QUALITY (P4, P5)	140
PLS_PRIO (P4)	141

Topic	Page
(PLS_)PUNCH (P4, P5)	142
(PLS_)PUNCH_TYPE (P4, P5)	143
PLS_RECEIVER (P4)	144
PLS_RECEIVER_BCC (P4)	145
PLS_RECEIVER_CC (P4)	146
PLS_ROTATE (P4)	147
PLS_SAVE_SPOOLFILE (P4)	148
scaleFactor (P5)	149
scaleMode (P5)	150
PLS_SCALE_TYPE (P4)	152
PLS_SCRNODE (P4)	154
(PLS_)SECUREPRINT (P4, P5)	155
PLS_SENDER (P4)	156
PLS_SET_COPY (P4)	157
PLS_SET_MEMBER_NAME (P4)	158
PLS_SET_NAME (P4)	159
PLS_SET_NUMBER (P4)	160
(PLS_)SORT (P4, P5)	161
(PLS_)SORT_TYPE (P4, P5)	162
PLS_SPLITTYPE (P4)	164
PLS_SRCAPPL (P4)	166
PLS_STAMP_0 (_n) (P4)	167
(PLS_)STAPLE (P4, P5)	169
(PLS_)STAPLE_TYPE (P4, P5)	170
PLS_START_TIME (P4)	171
PLS_STATISTIC_0 (_2) (P4)	172
PLS_SUBJECT (P4)	173
PLS_TEXTLINEWIDTH (P4)	174
(PLS_)TRAY_1 (_n) (P4, P5)	175
PLS_USEMETA (P4)	177
PLS_USERGROUP (P4)	178
(PLS_)USERNAME (P4, P5)	179

<b>Topic</b>	<b>Page</b>
PLS_WINDOW (P4)	180
PLS_WINDOW_PAGENUMBER (P4)	181
SEAL_CODEPAGE (P4)	182
SEAL_ORIGCODEPAGE (P4)	183

.....

## PLS\_ACCOUNT\_KEY (P4)

### purpose

PLS\_ACCOUNT\_KEY specifies the cost center.



### hints

- PLS\_ACCOUNT\_KEY is used in the flagpage, the statistic file and as distribution information.
- The job parameters (PLS\_)COSTCENTER, PLS\_DEPARTMENT und PLS\_AUX\_KOSTENSTELLE may contain the cost center also. PLS\_ACCOUNT\_KEY has the highest and PLS\_DEPARTMENT the lowest priority.
- (PLS\_)COSTCENTER is used in the printer driver templates.

### type

The job parameter is optional.

### job type

The job parameter is valid for single jobs and set collations.

### values

The value is specified as a string with up to 64 characters.

### default

There is no default.



### related parameters

- *(PLS\_)COSTCENTER (P4, P5)*, page 59
- *PLS\_DEPARTMENT (P4)*, page 69
- *PLS\_AUX\_KOSTENSTELLE (P4)*, page 49

## PLS\_AUX\_ABSENDER (P4)

.....  
PLS\_AUX\_ABSENDER specifies the sender.  
.....

purpose

.....  
PLS\_AUX\_ABSENDER is used in the flagpage, the statistic file and as distribution information.  
.....



.....  
The job parameter is optional.  
.....

type

.....  
The job parameter is valid for single jobs and set collations.  
.....

job type

.....  
The value is specified as a string with up to 256 characters.  
.....

values

.....  
There is no default.  
.....

default

## PLS\_AUX\_ABTEILUNG (P4)

purpose

.....  
PLS\_AUX\_ABTEILUNG specifies the department.  
.....



hint

PLS\_AUX\_ABTEILUNG is used in the flagpage, the statistic file and as distribution information.  
.....

type

The job parameter is optional.  
.....

job type

The job parameter is valid for single jobs and set collations.  
.....

values

The value is specified as a string with up to 256 characters.  
.....

default

There is no default.  
.....



## PLS\_AUX\_KOSTENSTELLE (P4)

PLS\_AUX\_KOSTENSTELLE specifies the cost center.

purpose

- PLS\_AUX\_KOSTENSTELLE is used in the flagpage, the statistic file and as distribution information.
- The job parameters PLS\_ACCOUNT\_KEY, (PLS\_)COSTCENTER and PLS\_DEPARTMENT may also contain the cost center. PLS\_ACCOUNT\_KEY has the highest and PLS\_DEPARTMENT the lowest priority.
- (PLS\_)COSTCENTER is used for the cost center in the printer driver templates.



hints

The job parameter is optional.

type

The job parameter is valid for single jobs and set collations.

job type

The value is specified as a string with up to 64 characters.

values

There is no default.

default

→ *PLS\_ACCOUNT\_KEY (P4)*, page 46

→ *(PLS\_)COSTCENTER (P4, P5)*, page 59

→ *PLS\_DEPARTMENT (P4)*, page 69



related parameters

## PLS\_AUX\_STANDORT (P4)

purpose

.....  
PLS\_AUX\_STANDORT specifies the location or the cost center.  
.....



hint

PLS\_AUX\_STANDORT is used in the flagpage, the statistic file and as distribution information.  
.....

type

The job parameter is optional.  
.....

job type

The job parameter is valid for single jobs and set collations.  
.....

values

The value is specified as a string with up to 256 characters.  
.....

default

There is no default.  
.....

## PLS\_AUX\_TELEFON (P4)

.....  
PLS\_AUX\_TELEFON specifies the telephone extension.  
.....

purpose

.....  
PLS\_AUX\_TELEFON is used in the flagpage, the statistic file and as distribution information.  
.....

 hint

.....  
The job parameter is optional.  
.....

type

.....  
The job parameter is valid for single jobs and set collations.  
.....

job type

.....  
The value is specified as a string with up to 256 characters.  
.....

values

.....  
There is no default.  
.....

default

## (PLS\_)BOOKLET (P4, P5)

purpose

(PLS\_)BOOKLET specifies if the document is output as a booklet.



hints

- (PLS\_)BOOKLET is only supported in PLOSSYS 5 if the sorting of the pages is done by the output device.
- If (PLS\_)BOOKLET is set, commands for the folding and stapling are passed to the output device if possible. This is independent of if the sorting of the pages is done by the output device.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

The value is specified as a Boolean:

- Y  
The document is output as a booklet.
- N  
The document will be output in unchanged order.

default

Default is N.



related parameters

→ (PLS\_)STAPLE (P4, P5), page 169

→ (PLS\_)STAPLE\_TYPE (P4, P5), page 170

## PLS\_CALL\_CONDITIONS (P4)

PLS\_CALL\_CONDITIONS specifies under which conditions an external program call is started.

purpose

- All job statuses supported by Infoserver can be used as a condition.
- The external program call is specified by the job parameter PLS\_SRCAPPL.

 hints

You find a list of all valid job status types in:

→ [INFOCLT\_TEC]

 reference

The job parameter is optional.

type

The job parameter is valid for single jobs and set collations.

job type


The value is specified as a string.

values

There is no default.

default

→ *PLS\_SRCAPPL (P4)*, page 166

 related parameters

## PLS\_CDBAN (P4)

purpose

PLS\_CDBAN specifies the initials or the department.



hint

PLS\_CDBAN is used in the flagpage, the statistic file and as distribution information.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

The value is specified as a string with up to 256 characters.

default

There is no default.

## PLS\_CDKUR (P4)

.....  
PLS\_CDKUR specifies the messenger office.  
.....

purpose

.....  
PLS\_CDKUR is used in the flagpage, the statistic file and as distribution information.  
.....

 hint

.....  
The job parameter is optional.  
.....

type

.....  
The job parameter is valid for single jobs and set collations.  
.....

job type

.....  
The value is specified as a string with up to 256 characters.  
.....

values

.....  
There is no default.  
.....

default

## (PLS\_)COLLATE (P4, P5)

purpose

(PLS\_)COLLATE specifies the type of sorting with copies.



hint

PLOSSYS 5 will ignore (PLS\_)COLLATE if the seal-copier service is used to create copies. In this case, the complete order will be executed multiple times (equals (PLS\_)COLLATE set to Y).

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set members.

values

The value is specified as a Boolean:

- Y  
The sorting with four copies and two sheets will be 1,2,1,2,1,2,1,2.
- N  
The sorting with four copies and two sheets will be 1,1,1,1,2,2,2,2.


default


Default is Y.



## PLS\_CONVERTER\_CFG (P4)

PLS\_CONVERTER\_CFG specifies the configuration file of the otf2pdf converter. purpose

- The directory where the configuration file is located can be specified in the PLOSSYS 4 settings.  hints
- The configuration file has to be located in the same directory as the default configuration file, default.cfg.
- Unless PLS\_CONVERTER\_CFG has been set, the default configuration file, default.cfg, is used.

→ [NETDOME\_SETTINGS\_TEC]  reference

The job parameter is optional. type

The job parameter is valid for single jobs and set members. job type

The value is specified as a string with up to 256 characters. The file name has to be specified without directory. values

Default is server\plotserv\gates\sap2pdf\default.cfg. default

## PLS\_COST\_TYPE (P4)

purpose

PLS\_COST\_TYPE specifies the PLOSSYS 4 console type from which the job is sent.



hint

PLS\_COST\_TYPE is set when repeating a job.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

You can specify the following values:

Value	Description
OPER	The job is sent via a local operating console or an operator console.
USER	The job is sent via any user console.

default

Default is USER.

## (PLS\_)COSTCENTER (P4, P5)

.....  
 (PLS\_)COSTCENTER specifies the cost center.  
 .....

purpose

- (PLS\_)COSTCENTER is used in the printer driver templates.
  - In PLOSSYS 4, the job parameters PLS\_ACCOUNT\_KEY, PLS\_AUX\_KOSTENSTELLE and PLS\_DEPARTMENT may contain the cost center too. PLS\_ACCOUNT\_KEY has the highest and PLS\_DEPARTMENT the lowest priority.
- .....

 hints

.....  
 The job parameter is optional.  
 .....

type

.....  
 The job parameter is valid for single jobs.  
 .....

job type

.....  
 The value is specified as a string with up to 64 characters.  
 .....

values


.....  
 There is no default.  
 .....

default

.....  
 → PLS\_ACCOUNT\_KEY (P4), page 46

→ PLS\_AUX\_KOSTENSTELLE (P4), page 49

→ PLS\_DEPARTMENT (P4), page 69  
 .....

 related pa-  
rameters

## PLS\_CREATE\_COVER (P4)

purpose

PLS\_CREATE\_COVER specifies if a cover sheet will be created.



hint

PLS\_CREATE\_COVER item overwrites the settings in PLOSSYS 4 settings.



reference

→ [NETDOME\_SETTINGS\_TEC]

type

The job parameter is optional.

job type

The job parameter is valid for set collations.

values

The value is specified as a Boolean:

- Y  
A cover sheet is created.
- N  
A cover sheet is not created.

default

Default is Y.



related parameters

→ *PLS\_CREATE\_TRAILER (P4)*, page 61

## PLS\_CREATE\_TRAILER (P4)

PLS\_CREATE\_TRAILER specifies if a cover sheet will be created.

purpose

PLS\_CREATE\_TRAILER item overwrites the settings in PLOSSYS 4 settings.

 hint

→ [NETDOME\_SETTINGS\_TEC]

 reference

The job parameter is optional.

type

The job parameter is valid for set collations.

job type

The value is specified as a Boolean:

values

- Y  
A trailer sheet is created.
- N  
A trailer sheet is not created.

Default is Y.

default

→ (PLS\_)DATA\_0 (\_9) (P4, P5), page 66

 parameter

## PLS\_CROP (P4)

### purpose

PLS\_CROP specifies the cropped window which is considered at the output of the job. In contrast to the specification in meters with PLS\_WINDOW, percent numbers are specified with PLS\_CROP.



### hints

- Based on the values of PLS\_PLOTSIZE and PLS\_CROP, the values in PLS\_WINDOW are calculated.
- After the calculation, the PLS\_CROP job parameter will be deleted.

### type

The job parameter is optional.

### job type

The job parameter is valid for single jobs.

### values

The values are specified as four percent numbers (float values). The values are separated by blanks.

- *margin\_top margin\_left width height*

### default

There is no default. If the job parameter is missing, PLS\_WINDOWS is not calculated.



### related parameters

→ *PLS\_WINDOW (P4)*, page 180

→ *PLS\_PLOTSIZE (P4)*, page 134

## PLS\_CROP\_MARKS (P4)

PLS\_CROP\_MARKS specifies if crop marks are set.

purpose

PLS\_CROP\_MARKS is only evaluated if CROP\_MARKS\_GENERATE has been set to Y in plossys.cfg.

 hint

The job parameter is optional.

type

The job parameter is valid for single jobs and set collations.

job type

The value is specified as a Boolean:

values

- Y  
Crop marks are generated.
- N  
Crop marks are not generated.

Default is N.

default

## PLS\_CRYPT (P4)

purpose

PLS\_CRYPT specifies if the spool file is encoded by the pdfauthorize program.

 hints

- PLS\_CRYPT is only evaluated if the output type is set to MAIL.
- The options for the encoding of the file are set via the PLS\_CRYPT\_OPTIONS keyword.
- If \$PLS\_CRYPT=Y is set in a set header, all set members are encoded.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.


values

The value is specified as a Boolean:

- Y  
The PDF file is encoded by the pdfauthorize program.
- N  
The PDF file is not encoded by the pdfauthorize program.

default

Default is N.

 related parameters

→ *PLS\_CRYPT\_OPTIONS (P4)*, page 65



## PLS\_CRYPT\_OPTIONS (P4)

.....  
 PLS\_CRYPT\_OPTIONS specifies the options which are passed to the pdfauthorize program. purpose

→ [PDFTOOLS\_TEC]

.....  
 PLS\_CRYPT\_OPTIONS is only evaluated if the output type is set to MAIL.



hint

.....  
 The job parameter is mandatory if \$PLS\_CRYPT is set to Y.

type

.....  
 The job parameter is valid for single jobs and set collations.

job type

.....  
 All options of the pdfauthorize program are valid.

values

.....  
 The defaults of the pdfauthorize program apply.


default

.....  
 → *PLS\_CRYPT (P4)*, page 64



related pa-  
rameters

## (PLS\_)DATA\_0 (\_9) (P4, P5)

purpose	<p>.....</p> <p>(PLS_)DATA_0 to (PLS_)DATA_9 are used for any information. The usage depends on the customer-specific processes and templates.</p> <p>.....</p>
type	<p>.....</p> <p>The job parameter is optional.</p> <p>.....</p>
job type	<p>.....</p> <p>The job parameter is valid for single jobs.</p> <p>.....</p>
values	<p>.....</p> <p>The value is specified as a string with up to 59 characters.</p> <p>.....</p>
default	<p>.....</p> <p>There is no default.</p> <p>.....</p>
 related parameters	<p>.....</p> <p>→ (PLS_)DUMMY_0 (_9) (P4, P5), page 71</p> <p>→ (PLS_)INFO_0 (_9) (P4, P5), page 87</p> <p>.....</p>

## PLS\_DEBUG (P4)

PLS\_DEBUG specifies which log messages are written.

purpose

PLS\_DEBUG is evaluated by GEKKO in the output driver.

 hint

The job parameter is optional.

type

The job parameter is valid for single jobs and set collations.

job type

The value is specified as a Boolean:

values

- Y  
All log messages specified in the [Job\Start\InsertLog] section of server\plotserv\plotter\printer.pcfg are written to the printer.log log file.
- N  
No log messages are written to the printer.log log file.

Default is N.

default

## PLS\_DELTYPE (P4)

### purpose

PLS\_DELTYPE specifies the deletion time of the jobs.



### hints

- The time interval after which the job will be deleted, is set in the [TIME\_DEF] section of de124h.dat to 1 hour as default.
- Within this period of time, the job can be output again.
- If the job is repeated or changed, the period of time is recalculated.
- The [NO\_DELETE] section specifies several days or periods of time in which no jobs are deleted.

### type

The job parameter is optional.

### job type

The job parameter is valid for single jobs and set collations.

### values

You can specify the following values:

Value	Description
AFTOUT	The job is immediately deleted after output.
NODEL	The job can only explicitly be deleted via PLOSSYS OCON.
AFT24H	The job is deleted after a specified time interval. The time interval is specified in server\plotserv\de124h.dat.

### default

Default is AFT24H.

## PLS\_DEPARTMENT (P4)

PLS\_DEPARTMENT specifies the department or cost center.

purpose

- PLS\_DEPARTMENT is used in PLOSSYS 4 in the flagpage, the statistic file and as distribution information.
- The PLS\_ACCOUNT\_KEY and PLS\_AUX\_KOSTENSTELLE job parameters may contain the cost center, too. PLS\_ACCOUNT\_KEY has the highest and PLS\_DEPARTMENT the lowest priority.
- (PLS\_)COSTCENTER is used in the printer driver templates.

 hints

The job parameter is optional.

type

The job parameter is valid for single jobs.

job type

The value is specified as a string with up to 64 characters.

values


There is no default.

default

→ *PLS\_ACCOUNT\_KEY (P4)*, page 46

→ *PLS\_AUX\_KOSTENSTELLE (P4)*, page 49

→ *(PLS\_)COSTCENTER (P4, P5)*, page 59

 related parameters

## PLS\_DIFBACKSTP (P4)

### purpose

PLS\_DIFBACKSTP specifies the stamp layout file for stamping the back sides in multi-page files.



### hints

- If \$PLS\_DIFBACKSTP==Y is set, the xxx.pts stamp layout file is used for stamping the back sides of a multi-page file.
- Thereby, xxx is the name of the stamp layout file which is used for stamping the front side of a multi-page file.
- The structure and the syntax of the stamp layout file for the back sides are the same as for the front sides and the single page files.
- The file extension of the stamp layout files for the front or single page files is .stp, the file extension for the back sides is .pts.
- PLS\_DIFBACKSTP is evaluated for multi-page files only.

### type

The job parameter is optional.

### job type

The job parameter is valid for single jobs.

### values

The value is specified as a Boolean:

- Y  
Different stamp layout files are used for the front side and back side of multi-page files.
- N  
The same stamp layout file is used for the front side and back side of multi-pages files.

### default

Default is N.



### related parameters

- *(PLS\_)DUPLEX (P4, P5)*, page 72
- *PLS\_ONLYFIRSTSTP (P4)*, page 116
- *PLS\_PAGES (P4)*, page 119
- *PLS\_WINDOW\_PAGENUMBER (P4)*, page 181

## (PLS\_)DUMMY\_0 (\_9) (P4, P5)

.....  
 (PLS\_)DUMMY\_0 to (PLS\_)DUMMY\_9 specifies company-specific items. The usage depends on the customer-specific processes and templates. purpose

.....  
 The job parameter is optional. type


.....  
 The job parameter is valid for single jobs. job type

.....  
 The value is specified as a string with up to 59 characters. values

.....  
 There is no default. default

.....  
 → (PLS\_)DATA\_0 (\_9) (P4, P5), page 66

→ (PLS\_)INFO\_0 (\_9) (P4, P5), page 87

 related parameters

## (PLS\_)DUPLEX (P4, P5)

purpose

(PLS\_)DUPLEX specifies the duplex printing for multi-page files.



hint

(PLS\_)DUPLEX is evaluated for multi-page files only.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs.

values PLOSSYS 4

In PLOSSYS 4, you can specify the following values:

Value	Description
LEFT_JOB_SIDE	The job is output in duplex printing with the left side as binding edge. With portrait pages, LEFT_JOB_SIDE behaves as LONG_SIDE, with landscape pages as SHORT_SIDE.
LEFT_SIDE	The job is output in duplex printing with the left side as binding edge. Here, left corresponds to the virtual paper. If VECTOR_SIZE of the used paper is configured as portrait (e. g. DINA4_P), LEFT_SIDE behaves as LONG_SIDE, with landscape (e. g. DINA4_L), LEFT_SIDE behaves as SHORT_SIDE.
LONG_SIDE	The job is output in duplex printing with the long side as binding edge.
NONE	The job is output in simplex printing.
SHORT_SIDE	The job is output in duplex printing with the short side as binding edge.
TOP_JOB_SIDE	The job is output in duplex printing with the top side as binding edge. With portrait pages, TOP_JOB_SIDE behaves as SHORT_SIDE, with landscape pages as LONG_SIDE.
TOP_SIDE	The job is output in duplex printing with the top side as binding edge. Here, top corresponds to the virtual paper. If VECTOR_SIZE of the used paper is configured as portrait (e. g. DINA4_P), TOP_SIDE behaves as SHORT_SIDE. With landscape formats (e. g. DINA4_L), TOP_SIDE behaves as LONG_SIDE.

..... *To be continued*



**(PLS\_)DUPLEX (P4, P5)**, Continuation

.....  
 In PLOSSYS 5, you can specify the following values:

values PLOSSYS 5

Value	Description
LONG_SIDE	The job is output in duplex printing with the long side as binding edge.
NONE	The job is output in simplex printing.
SHORT_SIDE	The job is output in duplex printing with the short side as binding edge.

.....  
 Default is NONE.


default

.....  
 → *PLS\_DIFBACKSTP (P4)*, page 70

→ *PLS\_ONLYFIRSTSTP (P4)*, page 116

→ *PLS\_PAGES (P4)*, page 119

→ *PLS\_WINDOW\_PAGENUMBER (P4)*, page 181  
 .....

 related pa-  
rameters

## (PLS\_)ENABLE\_SECUREPRINT (P4, P5)

purpose

(PLS\_)ENABLE\_SECUREPRINT specifies if (PLS\_)SECUREPRINT is taken into account.



hint

The evaluation of (PLS\_)ENABLE\_SECUREPRINT and (PLS\_)SECUREPRINT depend on the support by the output device and the driver template. For small format templates, this support is usually given, except for the generic templates for example.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs.

values

The value is specified as a Boolean:

- Y  
(PLS\_)SECUREPRINT is taken into account, that means when a password has been specified with (PLS\_)SECUREPRINT, the user has to specify this at the output device in order to output the job.
- N  
(PLS\_)SECUREPRINT is not taken into account, that means when a password has been specified with (PLS\_)SECUREPRINT, the user does not have to specify this at the output device in order to output the job.

default

By default, the job parameter is not set. This corresponds to the value Y.



related parameters

→ (PLS\_)SECUREPRINT (P4, P5), page 155

## PLS\_EXECNODE (P4)

PLS\_EXECNODE specifies the server name where PLOSSYS 4 runs.

purpose

PLS\_EXECNODE is evaluated by the conversion service and added to the header.

 hint

The job parameter is mandatory.

type

The job parameter is valid for single jobs and set collations.

job type

The value is specified as a string with up to 64 characters.

values

Default is the value of the NODE\_NAME keyword in `plossys.cfg`.

default

## PLS\_FIXLW (P4)

purpose	PLS_FIXLW specifies the line width at scaling.
type	The job parameter is optional.
job type	The job parameter is valid for single jobs.
values	The value is specified as a Boolean: <ul style="list-style-type: none"><li>• Y Line widths are not scaled together with the job.</li><li>• N Line widths are scaled together with the job.</li></ul>
default	Default is N.

## PLS\_FLAGPAGE (P4)

.....  
 PLS\_FLAGPAGE specifies the format of the flagpage which is printed on the the document of the job. purpose

.....  
 The job parameter is optional. type

.....  
 The job parameter is valid for single jobs. job type

.....  
 The value is specified as a Boolean: values

- Y  
The flagpage is output on the document.
- N  
No flagpage is output on the document.

.....  
 Default is N. default

.....  
 In this context, the following keywords in `plossys.cfg` are relevant: relevant key-words

→ `FP_GENERATE`, [NETDOME\_TEC]

→ `FLAGPAGE_FORMAT`, [NETDOME\_TEC]



## (PLS\_)FOLD (P4, P5)

purpose

(PLS\_)FOLD specifies if the documents of a job are folded.

 hints

- The output device has to be connected to a controllable folding device.
- (PLS\_)FOLD is only evaluated if a folding device is connected.

background knowledge

The job parameter is evaluated by the output script of the output device.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs.


values

The value is specified as a Boolean:

- Y  
The job is folded according to the specified folding rule. The fold type is specified with the (PLS\_)FOLD\_TYPE job parameter.
- N  
The documents of a job are not folded after output.

default

Default is N.

 related parameters

→ (PLS\_)FOLD\_TYPE (P4, P5), page 79

## (PLS\_)FOLD\_TYPE (P4, P5)

(PLS\_)FOLD\_TYPE specifies the fold type.

purpose

- The output device has to be connected to a controllable folding device and has to support the specified fold type.
- (PLS\_)FOLD\_TYPE is ignored if no folding device is connected.
- With large formats, (PLS\_)FOLD\_TYPE is only evaluated if (PLS\_)FOLD is set to Y.
- With small formats, it is always folded if (PLS\_)FOLD\_TYPE is set except (PLS\_)FOLD is set to N.



hints

The job parameter is optional.

type

The job parameter is valid for single jobs.

job type

In PLOSSYS 4, you can specify the following values for large formats:

values for large format

Value	Description
DINA_Heftrand	Package folding 210 mm x 297 mm (DIN A4) with binding margin of 20 mm
DINA_Heftstr	Package folding with attached filing strip; the exact folding size depends on the the folding device
Paket210	Package folding 210 mm x 297 mm without binding margin

In PLOSSYS 4 and PLOSSYS 5, you can specify the following values for small formats:


values for small format

Value	Description
CenterFold	Z folding
ZFold	Center folding

There is no default.

default

→ (PLS\_)FOLD (P4, P5), page 78

 related parameters

## PLS\_FORM\_STYLE (P4)

purpose

PLS\_FORM\_STYLE specifies the XSLT style sheets which are used during the creation of the additional sheets for a job.



hint

By default, the language of the additional sheets corresponds to the language of the PLOSSYS 4 server.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

The value is interpreted as the name of a subdirectory of `conf\common\forms`. The following files have to be available in the subdirectory:

- `cover.xml`
- `error.xml`
- `missing.xml`
- `trailer.xml`

Unless the subdirectory is found, the default is used.

default

Default is `default_${ENV.PLS_LANG}`.



example

The `PLS_LANG` environment variable is set to `de`. The additional sheets in German are used:

```
PLS_FORM_STYLE = default_de
```



related parameters

→ *PLS\_CREATE\_COVER (P4)*, page 60

→ *PLS\_CREATE\_TRAILER (P4)*, page 61



## PLS\_GATE\_OUTPUT (P4)

.....  
PLS\_GATE\_OUTPUT specifies in which directory the job is transferred for further processing. purpose

.....  
PLS\_GATE\_OUTPUT is evaluated in the gates.  hint



.....  
The job parameter is optional. type

.....  
The job parameter is valid for single jobs. job type

.....  
The value is specified as a string. values

.....  
By default, the job is moved to the main gate. default

## PLS\_GKS\_COLTAB (P4)

purpose	PLS_GKS_COLTAB specifies the file name of the GKS color table.
type	The job parameter is optional.
job type	The job parameter is valid for single jobs.
values	The value is specified as a string with up to 14 characters.
 hint	A job-specific color table is used, if the \$PLS_GKS_COLTAB job parameter is set to *. The job-specific color table has the name of the job and the .c1t file extension. It is stored with the header, the graphic file and the trigger file in the gate directory. The file containing the color table has to be transferred to the input directory before the trigger file.
default	By default, the color table of the GKS driver is used.
 examples	<p>The color table of the GKS driver is used:</p> <pre>\$PLS_GKS_COLTAB == ""</pre> <p>A job-specific color table is used:</p> <pre>\$PLS_GKS_COLTAB == "*"</pre>

## (PLS\_)GRAY (P4, P5)

.....  
 ((PLS\_)GRAY specifies if the document is output in gray scales.  
 .....

purpose

.....  
 In PLOSSYS 4, (PLS\_)GRAY has to be set due to the manager cannot handle  
 unknown values in (PLS\_)PLOTPEN.  
 .....

 hint

.....  
 The job parameter is optional.  
 .....

type

.....  
 The job parameter is valid for single jobs and set collations.  
 .....

job type

.....  
 The value is specified as a Boolean:  
 .....


values

- Y  
   The document is output in gray scales.
- N  
   The document is output unchanged.

.....  
 Default is N.  
 .....

default

.....  
 → (PLS\_)PLOTPEN (P4, P5), page 132  
 .....

 related pa-  
 rameters

## PLS\_GS\_TIMEOUT (P4)

purpose

.....  
PLS\_GS\_TIMEOUT specifies the conversion of a PDF page by Ghostscript is allowed to take as a maximum. If the time interval is exceeded, the conversion is aborted.  
.....



hint

.....  
PLS\_GS\_TIMEOUT overwrites the settings of the GS\_DEFAULT\_TIMEOUT keyword in plossys.cfg.  
.....

type

.....  
The job parameter is mandatory.  
.....

job type

.....  
The job parameter is valid for single jobs and set collations.  
.....

values

.....  
The value is specified as an integer in seconds.  
.....

default

.....  
Default is 600.  
.....

## PLS\_HEADER\_TYPE (P4)

PLS\_HEADER\_TYPE specifies the job type. purpose

The job parameter is mandatory. type

The job parameter is valid for single jobs and set collations. job type

You can specify the following values: values

Value	Description
PLOT	The job is a single job.
SET_COLLATION	The job is a set collation.

Default is PLOT. default

## PLS\_HOLD (P4)

purpose	..... PLS_HOLD specifies if the job remains in the maingate until the further processing is released by PLOSSYS OCON explicitly. .....
type	..... The job parameter is optional. .....
job type	..... The job parameter is valid for single jobs and set collations. .....
values	..... The value is specified as a Boolean: <ul style="list-style-type: none"><li>• Y The job remains in the maingate. The job for has to be released explicitly in PLOSSYS OCON for further processing.</li><li>• N According to the header settings, the job is further processed.</li></ul> .....
default	..... Default is N. .....

## (PLS\_)INFO\_0 (\_9) (P4, P5)

(PLS\_)INFO\_0 to (PLS\_)INFO\_9 specifies additional flagpage or label lines. The usage depends on the customer-specific processes and templates.

purpose

- In PLOSSYS 4, two successive items are combined to a flagpage or labeling and are output in the border of the document.
- Upper and lower cases are not changed.
- Right-aligned spaces are not output.
- As soon as a text is assigned to the job parameter, the text is output in PLOSSYS 4 independent of the settings of the PLS\_FLAPAGE job parameter.

 hints

The job parameter is optional.

type

The job parameter is valid for single jobs.

job type

The value is specified as a string with up to 59 characters.


values

There is no default.

default

→ (PLS\_)DATA\_0 (\_9) (P4, P5), page 66

→ (PLS\_)DUMMY\_0 (\_9) (P4, P5), page 71

 related parameters

In this context, the following keywords in `plossys.cfg` are relevant in PLOSSYS 4:

relevant keywords

→ `FP_GENERATE`, [NETDOME\_TEC]

→ `FLAGPAGE_FORMAT`, [NETDOME\_TEC]

 reference

## PLS\_INTERNAL\_ID (P4)

purpose

PLS\_INTERNAL\_ID specifies the internal job ID for a set collation.



hints

- PLS\_INTERNAL\_ID is evaluated by the conversion service and added to the header.
- The internal job ID serves for the job tracking and is unique.

type

The job parameter is mandatory.

job type

The job parameter is valid for single jobs and set collations.

values

The value is specified as a string with up to 80 characters.

default

There is no default.



## PLS\_IPP\_IGNORE\_QUEUE (P4)

.....  
PLS\_IPP\_IGNORE\_QUEUE specifies if the IPP server does not accept a job if an output device queue which does not exist in PLOSSYS 4 has been specified in its header. purpose

.....  
The job parameter is optional. type

.....  
The job parameter is valid for single jobs. job type

.....  
The value is specified as a Boolean:

- Y  
The job will be accepted and get the ERROR status.
- N  
The job will not be accepted by the IPP server.

.....  
Default is N. default

## PLS\_JOB\_STAT (P4)

purpose

PLS\_PLOT\_STAT specifies the conversion status of a job.



hint

PLS\_JOB\_STAT is generated by the format converter.

type

The job parameter is mandatory.

job type

The job parameter is valid for single jobs.

values

You can specify the following values:

Value	Description
OK	The job has been converted successfully.
PLS_HED_ERROR	The header of the job is not correct.
PLS_MET_ERROR	The metafile of the job is not correct.
PPR_HED_ERROR	The header of the preprocessor is not correct.
PPR_MET_ERROR	The metafile of the preprocessor is not correct.

default

Default is OK.



related parameters

→ *PLS\_JOB\_STAT\_MSG (P4)*, page 91

## PLS\_JOB\_STAT\_MSG (P4)

.....  
 PLS\_JOB\_STAT\_MSG specifies the text of the conversion result.  
 .....

purpose

.....  
 PLS\_JOB\_STAT\_MSG is generated by the format converter.  
 .....

 hint

.....  
 The job parameter is mandatory.  
 .....

type

.....  
 The job parameter is valid for single jobs.  
 .....

job type


.....  
 The value is specified as a string with up to 79 characters.  
 .....

values

.....  
 There is no default.  
 .....

default

.....  
 → *PLS\_JOB\_STAT (P4)*, page 90  
 .....

 related pa-  
 rameters

## (PLS\_)JOBNAME (P5)

purpose

.....  
 (PLS\_)JOBNAME specifies the job name.  
 .....



hint

.....  
 In PLOSSYS 5, (PLS\_)JOBNAME is passed to the jobName job parameter, refer to →  
 (PLS\_)PLOTID (P4, P5), page 128.  
 .....

type

.....  
 The job parameter is optional.  
 .....

job type

.....  
 The job parameter is valid for single jobs.  
 .....

values

.....  
 The value is specified as a string with up to 79 characters.  
 .....

default

.....  
 There is no default.  
 .....



related pa-  
 rameters

.....  
 → (PLS\_)PLOTID (P4, P5), page 128  
 .....

## PLS\_LINEWIDTH (P4)

PLS\_LINEWIDTH specifies the nominal line width for vectors in meters.

purpose

- The value is multiplied by the line width specified in the GKS metafile by an escape function.
- The result is the text line width to be output.

 hints

The job parameter is optional.

type

The job parameter is valid for single jobs.

job type

The value is specified as a float with up to three digits before and six digits after the decimal point in meters.

values

Default is 0.001.

default

## PLS\_MAIL (P4)

purpose PLS\_MAIL specifies if a job is sent as an e-mail.

type The job parameter is optional.

job type The job parameter is valid for single jobs.

values The value is specified as a Boolean:

- Y  
The job is sent as an e-mail.
- N  
The job is not sent as an e-mail.

default Default is N.



related pa-  
rameters

- *PLS\_MAIL\_COMPRESS (P4)*, page 95
- *PLS\_MAIL\_FILENAME (P4)*, page 96
- *PLS\_MAIL\_MERGE\_PDF\_MEMBER (P4)*, page 97
- *PLS\_MAIL\_MESSAGE (P4)*, page 98
- *PLS\_MAIL\_MESSAGE\_TEXT\_TYPE (P4)*, page 99
- *PLS\_MAIL\_SEND\_ATTACHMENT (P4)*, page 100
- *PLS\_MAIL\_TEXTFILE (P4)*, page 101
- *PLS\_MAIL\_USE\_SET\_HEADER (P4)*, page 102
- *PLS\_MAIL\_USE\_TEXTFILE (P4)*, page 103
- *PLS\_MAIL\_ZIP (P4)*, page 104
- *PLS\_MAIL\_ZIP\_FILENAME (P4)*, page 105
- *PLS\_MAIL\_ZIP\_MEMBER (P4)*, page 106

## PLS\_MAIL\_COMPRESS (P4)

PLS\_MAIL\_COMPRESS specifies in which cases a spool file is compressed.

purpose

PLS\_MAIL\_COMPRESS is only evaluated if the output type is set to MAIL.

 hint

The job parameter is optional.

type

The job parameter is valid for single jobs and set collations.

job type

You can specify the following values:


values

Value	Description
ALL	Each file is compressed.
NATIVE	Only files with (PLS_)PLOTTYPE=="NATIVE" are compressed.
NONE	No files are compressed.

Default is NONE.

default

→ *PLS\_MAIL (P4)*, page 94

 related parameters

## PLS\_MAIL\_FILENAME (P4)

purpose

PLS\_MAIL\_FILENAME specifies the name of the attachment.



hint

PLS\_MAIL\_FILENAME is only evaluated if the output type is set to MAIL.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

The value is specified as a string.

default

There is no default.




related parameters

→ *PLS\_MAIL (P4)*, page 94



## PLS\_MAIL\_MERGE\_PDF\_MEMBER (P4)

PLS\_MAIL\_MERGE\_PDF\_MEMBER specifies if the set members of a set collation are merged. purpose

- PLS\_MAIL\_MERGE\_PDF\_MEMBER is only evaluated if the output type is set to MAIL.  hints
- PLS\_MAIL\_MERGE\_PDF\_MEMBER is only evaluated for PDF files.


The job parameter is optional. type

The job parameter is valid for single jobs and set collations. job type

The value is specified as a Boolean: values

- Y  
All set members are combined to one PDF file.
- N  
All set members remain as single PDF files.

Default is N. default

→ *PLS\_MAIL (P4)*, page 94  related parameters

## PLS\_MAIL\_MESSAGE (P4)

purpose

PLS\_MAIL\_MESSAGE specifies the item in the message filed of the e-mail.



hint

PLS\_MAIL\_MESSAGE is only evaluated if the output type is set to MAIL.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

The value is specified as a string.

default

Default is „Your data from PLOSSYS 4.“.



related pa-  
rameters

→ *PLS\_MAIL\_MESSAGE\_TEXT\_TYPE (P4)*, page 99



related pa-  
rameters

→ *PLS\_MAIL (P4)*, page 94

## PLS\_MAIL\_MESSAGE\_TEXT\_TYPE (P4)

PLS\_MAIL\_MESSAGE\_TEXT\_TYPE specifies the format in which the e-mail text is sent. purpose

PLS\_MAIL\_MESSAGE\_TEXT\_TYPE is only evaluated if the output type is set to MAIL.  hint

The job parameter is optional. type

The job parameter is valid for single jobs and set collations. job type


You can specify the following values: values

Value	Description
plain	The e-mail text is sent as normal text.
html	The e-mail text is sent in HTML format.

Default is plain. default

→ *PLS\_MAIL (P4)*, page 94

→ *PLS\_MAIL\_MESSAGE (P4)*, page 98

 related parameters

## PLS\_MAIL\_SEND\_ATTACHMENT (P4)

purpose

PLS\_MAIL\_SEND\_ATTACHMENT specifies if the spool file is sent within the e-mail text or as attachment.



hint

PLS\_MAIL\_SEND\_ATTACHMENT is only evaluated if the output type is set to MAIL.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

The value is specified as a Boolean:

- Y  
The file is sent as an e-mail attachment.
- N  
The file is sent within the text of the e-mail.

default

Default is Y.




related parameters

→ *PLS\_MAIL (P4)*, page 94

## PLS\_MAIL\_TEXTFILE (P4)

PLS\_MAIL\_TEXTFILE specifies the file which contains the text entered in the e-mail message field. purpose

PLS\_MAIL\_TEXTFILE is only evaluated if  hint

- the output type is set to MAIL.
- the \$PLS\_MAIL\_USE\_TEXTFILE job parameter is set to Y.

The job parameter is optional. type

The job parameter is valid for single jobs and set collations. job type

The value is specified as a string. values


The value can be specified in the following ways:

- Specification of the absolute path  
`$PLS_MAIL_TEXTFILE == "D:\project_x\data\mailbody.txt"`
- The file is passed as associated file with the job, data\plotserv\associated\pl<jobnumber>.txt. The file is only evaluated if a value for PLS\_MAIL\_TEXTFILE exists but the specified file does not exist.

There is no default. default

→ *PLS\_MAIL (P4)*, page 94

→ *PLS\_MAIL\_USE\_TEXTFILE (P4)*, page 103

 related parameters

## PLS\_MAIL\_USE\_SET\_HEADER (P4)

purpose

PLS\_MAIL\_USE\_SET\_HEADER specifies which job parameters are valid.

 hints

- PLS\_MAIL\_USE\_SET\_HEADER is only evaluated if the output type is set to MAIL.
- General settings, like PLS\_SENDER, PLS\_RECEIVER, PLS\_-SUBJECT, PLS\_-MAIL\_MESSAGE, are centrally specified in the set header.

type

The job parameter is optional.

job type

The job parameter is valid for set collations.


values

The value is specified as a Boolean:

- Y  
All job parameters of the set header apply to each set member. Mandatory or general job parameters do not have to be specified in the header (set member).
- N  
All mandatory items relevant for sending the e-mail have to be specified in each set member.

default

Default is Y.

 related parameters

→ *PLS\_MAIL (P4)*, page 94

## PLS\_MAIL\_USE\_TEXTFILE (P4)

PLS\_MAIL\_USE\_TEXTFILE specifies if the text of an e-mail message field is read from a file. purpose

- The file containing the text is specified via the PLS\_MAIL\_TEXTFILE job parameter.
- Unless PLS\_MAIL\_USE\_TEXTFILE is set, the value of the PLS\_MAIL\_MESSAGE job parameter is used for the e-mail message field.
- PLS\_MAIL\_USE\_TEXTFILE is only evaluated if the output type is set to MAIL.



hints

The job parameter is optional. type

The job parameter is valid for single jobs and set collations. job type

The value is specified as a string. values

There is no default. default

→ *PLS\_MAIL (P4)*, page 94

→ *PLS\_MAIL\_TEXTFILE (P4)*, page 101



related parameters

## PLS\_MAIL\_ZIP (P4)

purpose

PLS\_MAIL\_ZIP specifies if the attachment is compressed.



hints

- PLS\_MAIL\_ZIP is only evaluated if the output type is set to MAIL.
- The internal compressing program does not support a splitting of the file if the maximum file size is exceeded.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

The value is specified as a Boolean:

- Y  
The attachment is compressed.
- N  
The attachment is not compressed.

default

Default is N.



related parameters


→ *PLS\_MAIL (P4)*, page 94

→ *PLS\_MAIL\_COMPRESS (P4)*, page 95



## PLS\_MAIL\_ZIP\_FILENAME (P4)

PLS\_MAIL\_ZIP\_FILENAME specifies the name of the ZIP file. purpose

PLS\_MAIL\_ZIP\_FILENAME is only evaluated if the output type is set to MAIL and the \$PLS\_MAIL\_ZIP job parameter is set to Y.  hint

The job parameter is optional. type

The job parameter is valid for single jobs and set collations. job type


The value is specified as a string. values

There is no default. default

→ *PLS\_MAIL (P4)*, page 94

→ *PLS\_MAIL\_ZIP (P4)*, page 104

→ *PLS\_MAIL\_ZIP\_MEMBER (P4)*, page 106

 related parameters

## PLS\_MAIL\_ZIP\_MEMBER (P4)

purpose

PLS\_MAIL\_ZIP\_MEMBER specifies if the set member is included into the ZIP file.



hint

PLS\_MAIL\_ZIP\_MEMBER is only evaluated if the output type is set to MAIL.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs.

values

The value is specified as a Boolean:

- Y  
The set member is included into the ZIP file.
- N  
The set member is not included into the ZIP file.

default

Default is N.



related parameters

→ *PLS\_MAIL (P4)*, page 94

# PLS\_MARKER (P4)

.....	
PLS_MARKER specifies the nominal size of the mark.	purpose
.....	
The job parameter is optional.	type
.....	
The job parameter is valid for single jobs.	job type
.....	
The value is specified as a float with up to 14 characters in meters.	values
.....	
Default is 0.001.	default
.....	

## PLS\_MAXMAILSIZE (P4)

### purpose

PLS\_MAXMAILSIZE specifies the maximum size of the e-mails to be sent.



### hints

- PLS\_MAXMAILSIZE is only evaluated if the output type is set to MAIL.
- For sending the e-mail, the files have to be encoded to Base64. The encoding increases the size of the file.

### type

The job parameter is optional.

### job type

The job parameter is valid for single jobs and set collations.

### values

The value is specified as an integer in KB.

### default

Default is 5000000.



### example

The maximum size of the file to be sent is set to 5000000 KB:

```
$PLS_MAXMAILSIZE == "5000000"
```

The file has 450000 KB. For sending the e-mail, the file will be coded. The encoding increases the file to 5010000 KB. Thus, the file is not sent.

## mediaSize (P5)

mediaSize specifies the target format.

purpose

The target format can be any format configured in the correspondent PPD file.

 hint

For more information about specifying the target format in PLOSSYS 5, refer to the system description of PLOSSYS 5:

 reference

→ <https://plossys-5.docs.sealsystems.de/>

The job parameter is optional.

type

The job parameter is valid for single jobs.

job type

The following values can be specified:

values


Value	Description
AUTO	The format fitting first or best is used. If GXCFORMATRule = 1 is specified in the PPD file, the format which fits best to the aspect ration of the document will be used.
<FORMAT>	The target format can be any format configured in the correspondent PPD file.

Default is AUTO.

default

→ *scaleFactor (P5)*, page 149

→ *scaleMode (P5)*, page 150

 related parameters

## PLS\_META\_n (P4)

purpose

PLS\_META\_n specifies the PDF metadata with PDF/A files.

 hints

- With a set collation, PLS\_META\_n is set in the set header. A job parameter in a set member is not evaluated.
- With a set collation PLS\_META\_n is only evaluated if the \$PLS\_USEMETA job parameter is set to Y.
- PLS\_META\_n item is evaluated for the PDF/A processing by the output driver only.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.



..... *To be continued*

## PLS\_META\_n (P4), Continuation

You can specify the following values with the following syntax:

values

- *prefix:tag\_name=tag\_value*

Value	Description
<i>prefix</i>	<p>The following values are allowed:</p> <ul style="list-style-type: none"> <li>• xmp</li> <li>• dc</li> <li>• pdf</li> <li>• xmpMM</li> </ul>
<i>tag_name</i>	<p>The following characters are allowed:</p> <ul style="list-style-type: none"> <li>• a-z</li> <li>• A-Z</li> <li>• 0-9</li> <li>• -</li> </ul> <p> <b>hint - predefined tags:</b></p> <p>The following tags have a definite meaning. If these are specified, the prefix has not to be specified:</p> <ul style="list-style-type: none"> <li>• Title (pdf:title)</li> <li>• Author (pdf:creator)</li> <li>• Subject (pdf:subject)</li> <li>• Creator (xmp:CreatorTool)</li> <li>• Producer (pdf:Producer)</li> <li>• CreationDate</li> <li>• ModDate</li> </ul>
<i>tag_value</i>	<p>Any value.</p> <p> <b>hint - special character:</b></p> <p>When using the special character “, it has to be quoted by /.</p>


There is no default.

default

..... *To be continued*

## PLS\_META\_n (P4), Continuation


---

 example

.....  
The PDF meta tag includes the value SEAL Systems:

`$PLS_META_0 == "Author=SEAL Systems"`

---

 related parameters

→ *PLS\_USEMETA (P4)*, page 177

---



## PLS\_META\_TYPE (P4)

PLS\_META\_TYPE specifies the type of the document. By means of this, the additional sheets can be distinguished from "normal" documents by PLOSSYS OCON for example.

purpose

The job parameter is optional.

type

The job parameter is valid for single jobs.

job type

The following values are available:

values

Value	Description
CoverSheet	The document is a cover sheet.
Document	The document is a "normal" document.
ErrorSheet	The document is an error sheet.
MissingSheet	The document is a missing sheet if a document of a set collation cannot be output.
SplittingSheet	The document is a missing sheet if a document has been redirected to another output device when outputting to a pool device.
TrailerSheet	The document is a trailer sheet.

Default is Document.

default

## PLS\_MIRROR (P4)

purpose	PLS_MIRROR specifies the mirroring of jobs.
type	The job parameter is optional.
job type	The job parameter is valid for single jobs.
values	The value is specified as a Boolean: <ul style="list-style-type: none"><li>• Y The job is mirrored.</li><li>• N The job is not mirrored.</li></ul>
default	Default is N.

## PLS\_NETTO\_PLOTSIZE (P4)

PLS\_NETTO\_PLOTSIZE specifies the printable area of the page.

purpose

PLS\_NETTO\_PLOTSIZE is set by the CGM preprocessor.

 hint

The job parameter is optional.

type

The job parameter is valid for single jobs.

job type

The values are specified as four float values with up to three digits before and six digits after the decimal point. The values are separated by commas or blanks. The area is specified in meters.

values

- *XMIN, YMIN, XMAX, YMAX*

Default is 0.0 0.0 0.0 0.0.

default

## PLS\_ONLYFIRSTSTP (P4)

purpose

PLS\_ONLYFIRSTSTP specifies which pages of multi-page files are stamped.



hint

PLS\_ONLYFIRSTSTP is evaluated for multi-page files only.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs.

values

The value is specified as a Boolean:

- Y  
Only the first page of a multi-page file is stamped.
- N  
All pages of the multi-page file are stamped.

default

Default is N.



related parameters

→ *(PLS\_)DUPLEX (P4, P5)*, page 72

→ *PLS\_DIFBACKSTP (P4)*, page 70

→ *PLS\_PAGES (P4)*, page 119

→ *PLS\_WINDOW\_PAGENUMBER (P4)*, page 181

## PLS\_ORIG\_EXT (P4)

.....  
PLS\_ORIG\_EXT specifies the file extension of the original file.  
.....

purpose

.....  
Unless PLS\_ORIG\_EXT exists, it will be created by the conversion service.  
.....

 hint

.....  
The job parameter is optional.  
.....

type

.....  
The job parameter is valid for single jobs and set members.  
.....

job type

.....  
The value is specified as a string with up to 255 characters.  
.....

values

.....  
There is no default.  
.....

default

## (PLS\_)ORIG\_NAME (P4, P5)

purpose

(PLS\_)ORIG\_NAME specifies the original file name.



hints

- Unless (PLS\_)ORIG\_NAME exists, it will be created in PLOSSYS 4 by the conversion service.
- In PLOSSYS 5, (PLS\_)ORIG\_NAME is passed to the fileName job parameter. Further sources for fileName are:
  - SAP\_OMS\_S\_FILE (from SAP BC-XOM)
  - Field N in the LPR protocol
  - Standard IPP attribute document-name

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

The value is specified as a string with up to 255 characters.

default

There is no default.

## PLS\_PAGES (P4)

PLS\_PAGES specifies which pages of multi-page files are output.

purpose

- PLS\_PAGES is evaluated for multi-page files only.
- The pages to be output are specified and not the output order.



hints

The job parameter is optional.

type

The job parameter is valid for single jobs.

job type

The value is specified as a string:

values

- a-b area setting  
Pages a up to b are output.
- d, e or d;e explicit page specification; comma and semicolon are supported as separator.  
Pages d and e are output.

There is no default.

default

The pages 1 up to 5 of the multi-page file are output:


```
$PLS_PAGES == "1-5"
```

The pages 2 and 4 of the multi-page file are output:

```
$PLS_PAGES == "2,4"
```

The pages 1, 2 5 up to 8, 10, 12 up to 15 of the multi-page file are output:

```
$PLS_PAGES == „1,2,5-8,10,12-15“
```




example

→ *(PLS\_)DUPLEX (P4, P5)*, page 72

→ *PLS\_ONLYFIRSTSTP (P4)*, page 116

→ *PLS\_DIFBACKSTP (P4)*, page 70

→ *PLS\_WINDOW\_PAGENUMBER (P4)*, page 181



related parameters

## PLS\_PAPER\_OPT (P4)

.....  
purpose PLS\_PAPER\_OPT specifies the paper optimization.  
.....

type The job parameter is optional.  
.....

job type The job parameter is valid for single jobs.  
.....

values The value is specified as a Boolean:  

- Y  
Paper optimization is performed.
- N  
Paper optimization is not performed.

  
.....

default Default is N.  
.....



## PLS\_PDF\_OWNER\_PASSWD (P4)

PLS\_PDF\_OWNER\_PASSWD specifies the owner password of a PDF job.

purpose

- The owner password protects the document against undesired actions, like changing, printing, commenting, etc.
- If a PDF document is protected by an owner password, the value of the job parameter has to match the owner password. Otherwise, an output does not take place.

 hints

The job parameter is optional.

type

The job parameter is valid for single jobs.

job type


The value is specified as a string.

values

There is no default.

default

The PDF job is protected by the SAVE owner password. The job is only output if the following job parameter is set:

 example

```
$PLS_PDF_OWNER_PASSWD == "SAVE"
```

## PLS\_PDF\_PASSWD (P4)

purpose

PLS\_PDF\_PASSWD specifies the password for opening a PDF job.



hint

The user password protects the document against unauthorized opening. Without this password, the document cannot be opened. Adobe Reader asks for the password in a dialog.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs.

values

The value is specified as a string.

default

There is no default.



example

The PDF job is protected by the SAVE user password. The job is only output if the following job parameter is set:

```
$PLS_PDF_PASSWD == "SAVE"
```

# PLS\_PENTAB (P4)

.....	
PLS_PENTAB specifies the pen table which is used by the format converter.	purpose
.....	
The job parameter is optional.	type
.....	
The job parameter is valid for single jobs.	job type
.....	
The value is specified as a string with up to 14 characters.	values
.....	
There is no default.	default
.....	

## PLS\_PLOT\_FORMAT (P4)

purpose	PLS_PLOT_FORMAT specifies the format of the graphic file.
type	The job parameter is optional.
job type	The job parameter is valid for single jobs.
values	The value is specified as a string with up to 79 characters.
default	There is no default.

## PLS\_PLOT\_ROTATE (P4)

PLS\_PLOT\_ROTATE specifies the rotation of the job's documents.

purpose

- If a job contains several pages, the rotation is applied to all pages.
- The rotation is performed before the rotation by the output driver.

 hints

The job parameter is optional.

type

The job parameter is valid for single jobs.

job type

You can specify the following values:

values

Value	Description
0	The document will not be rotated.
90	The document will be rotated by 90 degrees.
180	The document will be rotated by 180 degrees.
270	The document will be rotated by 270 degrees.

Default is 0.

default

## (PLS\_)PLOTCOPY (P4, P5)

purpose

(PLS\_)PLOT\_COPY specifies the number of copies.



hint

In PLOSSYS 5, (PLS\_)PLOTCOPY is passed to the `copies` job parameter. Further sources for `copies` are:

- SAP\_OMS\_S\_COPIES (from SAP BC-XOM)
- WIN\_INF\_COPIES (set by SEAL MasterDriver)
- Standard IPP attribute `copies`

type

The job parameter is optional.

job type

The job parameter is valid for single jobs.

values

The value is specified as an integer.



hint

If the value is set to 0, only one copy of the job is output. If the value is less than 0 or greater than 99, the default is used.

default

Default is 0.




related parameters

→ *PLS\_SCRNODE (P4)*, page 154

## PLS\_PLOTDATE (P4)

.....  
PLS\_PLOTDATE specifies the time when the job was processed in PLOSSYS 4. purpose  
.....

Unless PLS\_PLOTDATE exists, it will be created by the conversion service.  hint  
.....

The job parameter is optional. type  
.....

The job parameter is valid for single jobs. job type  
.....

The value is specified as a string up to 19 characters in the following format: values

- yyyy-mm-ddThh:mm:ss
- .....

Default is the current date and the time at the processing in the conversion service. default  
.....

## (PLS\_)PLOTID (P4, P5)

purpose

.....  
(PLS\_)PLOTID specifies the name of the job. The job parameter is the identifier of the job.  
.....

 hints

- The job name is used in the log files and in the statistics files of PLOSSYS 4.
- In PLOSSYS 5, (PLS\_)PLOTID is passed to the jobName job parameter. Further sources for jobName are:
  - (PLS\_)JOBNAME
  - Field J in the LPR protocol
  - Standard IPP attribute job-name
- (PLS\_)PLOTID is used as name for Web Portal shares when they are generated automatically.

type

.....  
The job parameter is mandatory.  
.....

job type

.....  
The job parameter is valid for single jobs.  
.....

values

.....  
The value is specified as a string with up to 80 characters.  
.....


default

.....  
Default is the name of the graphic file.  
.....



## PLS\_PLOTITEM (P4)

.....  
PLS\_PLOTITEM specifies the number of the graphic file items (records) of the GKS metafile. purpose  
.....

PLS\_PLOTITEM is evaluated by the conversion service and added to the header.  hint  
.....

The job parameter is optional. type  
.....

The job parameter is valid for single jobs. job type  
.....

The value is specified as an integer in the range 0 to 999999. values

If the value is less than 0, the job parameter is set to 0.

.....  
There is no default. default  
.....

## (PLS\_)PLOT PAPER (P4, P5)

### purpose

(PLS\_)PLOT PAPER specifies the output medium.



### hints

- Unless the output device has been started in the No Request operation mode, PLOSSYS 4 requests operating if the job to be output does not match the media currently available in the output device or if the (PLS\_)PLOT PAPER keyword has been set for the job to SP.
- If an invalid value is set, the default is used.



### reference

For more information about the output on specific media, refer to → *Job on a Specific Medium (P4, P5)*, page 27.

### type

The job parameter is optional.

### job type

The job parameter is valid for single jobs.

### values

You can specify the following values:

Value	Description
BE	The job is output on the current medium type.
DB	The job is output on a cover sheet.
DE	The job is output on the default media type.
FO	The job is output on a film.
LI	The job is output on a light-weight paper.
MAN	The job is output on a tray which has to be controlled manually.
PA	The job is output on a paper.
SP	The job is output on a special medium.
SP1 ... SP12	The job is output on a special medium. Up to 12 different definitions of special media are possible.
TR	The job is output on a transparent medium.

..... *To be continued*

**(PLS\_)PLOT PAPER (P4, P5),** Continuation

As alternative values, PLOSSYS 5 supports the real names of the papers when the media types are passed to the output device directly:

alternative values in PLOSSYS 5

Name	Value
Color	DB
Transparency	F0
Plain	PA
Thin	LI
Vellum	TR
Letterhead	SP1
Preprinted	SP2
Bond	SP4
Recycled	SP5
Prepunched	SP6
Cardstock	SP7
Envelope	SP8
Rough	SP9
Thick	SP10
Coated	SP11
Highquality	SP12

Default is BE.

default

## (PLS\_)PLOTPEN (P4, P5)

purpose (PLS\_)PLOTPEN specifies the color type of the job.

type The job parameter is optional.

job type The job parameter is valid for single jobs.

values PLOSSYS 4 In PLOSSYS 4, you can specify the following values:

Value	Description
BE	Color information is not transferred to the output device.
EN	The color type which is set by the PEN_TYPE keyword in <code>plossys.cfg</code> is used.
KU	The job is output in color.
TU	The job is output in black & white without gray scales.



hint

Nowadays, PLOSSYS 4 often outputs the job in gray scales also with (PLS\_)PLOTPEN TU.

values PLOSSYS 5 In PLOSSYS 5, you can specify the following values:

Value	Description
BE	Color information is not transferred to the output device.
GR	The job is output in gray scales.
KU	The job is output in color.
TU	The job is output in gray scales.



hint

In PLOSSYS 5, (PLS\_)PLOTPEN TU, (PLS\_)PLOTPEN TU and (PLS\_)GRAY Y lead to the same result.

default

Default is BE.



related parameters

→ (PLS\_)GRAY (P4, P5), page 83

## PLS\_PLOTSCALE (P4)

PLS\_PLOTSCALE specifies the scaling.

purpose

PLOSSYS 4 distinguishes between the following possibilities to specify the scaling:

 hint

- Specifying the scaling factor
- Specifying the target format

The job parameter is optional.

type

The job parameter is valid for single jobs and set collations.

job type

- *Float*  
The value is specified as a float with up to three digits before and six digits after the decimal point.

values



Hint - precision:

With a larger number of digits, the value is shortened correspondingly.

- *String*  
The value is specified as a string up to 20 characters.



Hint - format name:


The value has to correspond to a format name which is specified by the `FORMAT_DEFINITIONS` keyword in `plossys.cfg`.

Default is 1.0.

default

→ [PLS\\_PLOTSIZE \(P4\)](#), page 134

→ [PLS\\_SCALE\\_TYPE \(P4\)](#), page 152

 related parameters

## PLS\_PLOTSIZE (P4)

purpose

PLS\_PLOTSIZE specifies the output format of the document.



hint

The output format is evaluated by the conversion service and added to the header.

type

The job parameter is mandatory.

job type

The job parameter is valid for single jobs.

values

The values are specified as four float values with up to three digits before and six digits after the decimal point. The values are separated by commas. The values are specified in meter. They refer to the scaling factor 1.0.

- *XMIN, YMIN, XMAX, YMAX*

default

Default is 0.0 0.0 0.0 0.0.



example

The output format is DIN A4 portrait:

```
$PLS_PLOTSIZE == 0.000000 0.000000 0.209900 0.297040
```



related parameters

→ *PLS\_PLOTSCALE (P4)*, page 133

→ *PLS\_SCALE\_TYPE (P4)*, page 152

## (PLS\_)PLOTTER (P4, P5)

.....  
 (PLS\_)PLOTTER specifies the name of the output device.  
 .....

purpose

- In PLOSSYS 4, (PLS\_)PLOTTER has to correspond to the value of the PLOT-TER\_NAME keyword in plossys.cfg.
  - In PLOSSYS 5, (PLS\_)PLOTTER is passed to the printerName. Further sources for printerName are:
    - SAP\_OMS\_S\_DEVICE (from SAP BC-XOM)
    - Field P in the LPR protocol
    - Standard IPP attribute job-printer-uri
- .....



hints

.....  
 The job parameter is mandatory.  
 .....

type

.....  
 The job parameter is valid for single jobs and set collations.  
 .....

job type

.....  
 The value is specified as a string with up to 29 characters.  
 .....

values

.....  
 There is no default.  
 .....

default

## (PLS\_)PLOTTYPE (P4, P5)

purpose

(PLS\_)PLOTTYPE specifies the graphic type.



hint

In PLOSSYS 4, graphic format types not belonging to the internal formats and without preprocessor for conversion are bypassed. They can only be output on output devices with the same entry as NATIVE\_CODE or ANY\_NATIVE in plossys.cfg.

type

The job parameter is mandatory.

job type

The job parameter is valid for single jobs.

values PLOSSYS  
4, part 1

In PLOSSYS 4, you can specify the following values:

Value	Format	Processing
ASCII	Text	Internal graphic format
C907	CalComp-907	<ul style="list-style-type: none"> <li>• Bypassing or converting into an internal graphic format via a preprocessor</li> <li>• Conversion into an internal graphic format with GXC engine</li> </ul>
CALS	CALS raster type 1 and 2	<ul style="list-style-type: none"> <li>• Only bypass possible</li> <li>• Internal graphic format when GXC Engine is active</li> </ul>
CATIA	Catia Image	Via Digital Process Factory
CDR	CorelDRAW	Via Digital Process Factory
CGM	Computer Graphics Metafile	Internal graphic format
DOC	MS Word	Via Digital Process Factory
DWG	Auto CAD	Via Digital Process Factory
GIF	Graphics Interchange Format	Internal graphic format
GKSMR	GKS file in record oriented format	Internal graphic format

..... *To be continued*



**(PLS\_)PLOTTYPE (P4, P5)**, Continuation

Continuation:

values PLOSSYS  
4, part 2

Value	Format	Processing
GKSMRW	See GKSMR The output format is taken from the header.	Internal graphic format
GKSMS	GKS file in streamed format	Internal graphic format
GKSMSW	See GKSMS The output format is taken from the header.	Internal graphic format
GXC	Symbolic identifier for formats processed by the GXC engine	Internal graphic format when GXC Engine is active
HCBS	HCBS	Internal graphic format
HPGL	HPGL, Hewlett-Packard Graphic Language	<ul style="list-style-type: none"> <li>• Bypassing or converting into an internal graphic format via a preprocessor</li> <li>• Internal graphic format when GXC Engine is active</li> </ul>
HPGL2	HPGL2, Hewlett-Packard Graphic Language 2	<ul style="list-style-type: none"> <li>• Bypassing or converting into an internal graphic format via a preprocessor</li> <li>• Internal graphic format when GXC Engine is active</li> </ul>
ILLEGAL	Invalid output device code	No processing
JPEG		
NATIVE	Any printer code	Only bypass possible

..... *To be continued*

**(PLS\_)PLOTTYPE (P4, P5)**, Continuation

values PLOSSYS  
4, part 3

Continuation:

Value	Format	Processing
NONE	Any printer code	
OTF	SAPGOF	Internal graphic format
PDF	PDF	Internal graphic format
POSTSCRIPT	PostScript	Bypassing or converting into an internal graphic format via a preprocessor
PPT	MS PowerPoint	Via Digital Process Factory
PRESCRIBE	Kyocera Prescribe Format	Only bypass possible
RTL	HP RTL	<ul style="list-style-type: none"> <li>• Only bypass possible</li> <li>• Internal graphic format when GXC Engine is active</li> </ul>
TIFF	TIFF	Internal graphic format
XSL	MS Excel	Via Digital Process Factory
XML	Extensible Markup Language	Internal graphic format

values PLOSSYS 5

In PLOSSYS 5, you can specify the following values:

Value	Format	Processing
NATIVE	Any printer code	Only bypass possible

default

There is no default.



hint

Other formats are available on request.

## PLS\_POOLPLOTTER\_ALL (P4)

.....  
 PLS\_POOLPLOTTER\_ALL specifies if a job is output on all devices specified as pool devices. purpose

.....  
 The job parameter is optional. type

.....  
 The job parameter is valid for single jobs. job type

.....  
 The value is specified as a Boolean: values

- Y  
 The job is output once on all devices specified as pool devices.
- N  
 The job is not output on all devices specified as pool devices.

.....  
 Default is N. default

## (PLS\_)PRINT\_QUALITY (P4, P5)

.....  
 purpose (PLS\_)PRINT\_QUALITY specifies the output quality of the job corresponding to the properties of the output device.  
 .....

.....  
 type The job parameter is optional.  
 .....

.....  
 job type The job parameter is valid for single jobs and set collations.  
 .....

.....  
 values You can specify the following values:

Value	Description
NORMAL	The job is output in normal quality.
HIGH	The job is output in high quality.
LOW	The job is output in low quality.

.....  
 default Default is NORMAL.  
 .....

## PLS\_PRIO (P4)

PLS\_PRIO specifies the priority of the job.

purpose

- Jobs with the priority 9 have the highest priority.
- Jobs with the priority 0 have the lowest priority.
- Arriving jobs are entered in the list of waiting jobs within their priority level.
- Only jobs with the priority 0 or 1 are taken into account for paper optimization.

 hints

The job parameter is optional.

type

The job parameter is valid for single jobs.

job type

The value is specified as an integer in the range 1 to 9.

values

Default is 0.

default

## (PLS\_)PUNCH (P4, P5)

purpose

(PLS\_)PUNCH specifies if the documents of the jobs are punched.



hint

The punch type is specified with the (PLS\_)PUNCH\_TYPE job parameter.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

You can specify the following values:

Value	Description
Y	The documents are punched according to the settings of the (PLS_)PUNCH_TYPE job parameter.
N	The document will not be punched.
any value (except of N)	The documents are punched according to the settings of the (PLS_)PUNCH_TYPE job parameter.

default

There is no default.



related parameters

→ (PLS\_)PUNCH\_TYPE (P4, P5), page 143

## (PLS\_)PUNCH\_TYPE (P4, P5)

(PLS\_)PUNCH\_TYPE specifies the position and the number of the holes.

purpose

- If the job parameter (PLS\_)PUNCH is set to Y, but (PLS\_)PUNCH\_TYPE is not defined or has an invalid value, the document will not be punched.
- Possible punch types depend on the ability of the output device.



hints

The job parameter is mandatory for set collation.

type

The job parameter is optional for single jobs.

The job parameter is valid for single jobs and set collations.

job type

You can specify the following values:


values

Value	Description
Left	The documents are punched with two holes on the margin left.
Bottom	The documents are punched with two holes on the margin bottom.
Right	The documents are punched with two holes on the margin right.
Top	The documents are punched with two holes on the margin top.
FourLeft	The documents are punched with four holes on the margin left.
FourBottom	The documents are punched with four holes on the margin bottom.
FourRight	The documents are punched with four holes on the margin right.
FourTop	The documents are punched with four holes on the margin top.

There is no default. If (PLS\_)PUNCH is set to Y, the default is LEFT.

default

→ (PLS\_)PUNCH (P4, P5), page 142



related parameters

## PLS\_RECEIVER (P4)

purpose

PLS\_RECEIVER specifies the e-mail address of the receiver.



hints

- PLS\_RECEIVER is only evaluated if the output type is set to MAIL.
- In the Web Portal, PLS\_RECEIVER is used as receiver of the share with the automatic generation of shares.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

The value is specified as a string. Several addresses are separated by commas.

default

There is no default.



related parameters

- *PLS\_RECEIVER\_CC (P4)*, page 146
- *PLS\_RECEIVER\_BCC (P4)*, page 145
- *PLS\_SENDER (P4)*, page 156
- *PLS\_SUBJECT (P4)*, page 173
- *PLS\_MAIL\_MESSAGE (P4)*, page 98



## PLS\_RECEIVER\_BCC (P4)

PLS\_RECEIVER\_BCC specifies the e-mail address of the additional receiver. Unlike to PLS\_RECEIVER\_CC, the original receiver (PLS\_RECEIVER) has no knowledge about the additional receivers.

purpose

PLS\_RECEIVER\_BCC is only evaluated if the output type is set to MAIL.

 hint

The job parameter is optional.

type

The job parameter is valid for single jobs and set collations.

job type

The value is specified as a string. Several addresses are separated by commas.

values

There is no default.


default

→ *PLS\_RECEIVER (P4)*, page 144

→ *PLS\_RECEIVER\_CC (P4)*, page 146

→ *PLS\_RECEIVER (P4)*, page 144

→ *PLS\_MAIL\_MESSAGE (P4)*, page 98

 related parameters

## PLS\_RECEIVER\_CC (P4)

purpose

PLS\_RECEIVER\_CC specifies the e-mail address of the additional receiver.



hint

PLS\_RECEIVER\_CC is only evaluated if the output type is set to MAIL.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

The value is specified as a string. Several addresses are separated by commas.

default

There is no default.



related parameters

→ *PLS\_RECEIVER (P4)*, page 144


→ *PLS\_RECEIVER\_BCC (P4)*, page 145

→ *PLS\_RECEIVER (P4)*, page 144

→ *PLS\_MAIL\_MESSAGE (P4)*, page 98

## PLS\_ROTATE (P4)

PLS\_ROTATE specifies the angle of the HPGL drawing in the preprocessor gate. purpose

PLS\_ROTATE is only evaluated in the hpg1gate.  hint

The job parameter is optional. type

The job parameter is valid for single jobs. job type

You can specify the following values: values

Value	Description
0	The drawing is not rotated.
90	The drawing is rotated by 90 degrees.
180	The drawing is rotated by 180 degrees.
270	The drawing is rotated by 270 degrees.

Default is 0. default

## PLS\_SAVE\_SPOOLFILE (P4)

purpose

PLS\_SAVE\_SPOOLFILE specifies if the spool files are deleted or saved.

 hints

- Controlling of the output device via script: SavePlotfile
- Controlling of the output device via GEKKO: SAVE\_SPOOLFILE

type

The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

The value is specified as a Boolean:

- Y  
The spool files are not deleted and are saved in the data\plotserv\spoolfiles directory.
- N  
The spool files are deleted after output.

default

Default is N.

## scaleFactor (P5)

.....  
scaleFactor specifies the manual scaling factor.  
.....

purpose

.....  
The parameter may only contain a single value, not different values for x and y.  
.....

 hint

.....  
For more information about specifying the target format in PLOSSYS 5, refer to the system description of PLOSSYS 5:

 reference

→ <https://plossys-5.docs.sealsystems.de/>  
.....

.....  
The job parameter is optional.  
.....

type

.....  
The job parameter is valid for single jobs.  
.....

job type


.....  
The value is specified as a float with decimal point.  
.....

values

.....  
Default is 1.0.  
.....

default

.....  
→ *mediaSize (P5)*, page 109

 related parameters

.....  
→ *scaleMode (P5)*, page 150  
.....

## scaleMode (P5)

purpose

scaleMode specifies the scaling mode for the automatic scaling.



hint

The parameter can also exist as printer parameter. The job parameter takes priority over the printer parameter.



reference

For more information about specifying the target format in PLOSSYS 5, refer to the system description of PLOSSYS 5:

→ <https://plossys-5.docs.sealsystems.de/>

type

The job parameter is optional.

job type

The job parameter is valid for single jobs.

values, part 1

You can specify the following values:

Value	Description
fitMedia-Size	<ul style="list-style-type: none"> <li>The complete format size is used for the document. The borders of the document which cannot be addressed by the hardware of the output device are clipped.</li> <li>Documents that are too large are scaled to the target format. A document that is larger than the tolerance area of the target format is scaled to the size of the printable area.</li> <li>Documents that are too small are placed on the target format without being scaled.</li> <li>Similar to DINSCL (P4)</li> </ul>
fitPrint-Area	<ul style="list-style-type: none"> <li>Only the printable area is used. The document is scaled down accordingly.</li> <li>Documents that are too small are placed on the target format without being scaled.</li> <li>Similar to MAXSCL (P4)</li> </ul>
clip	<ul style="list-style-type: none"> <li>The document will not be scaled automatically. The scaling factor scaleFactor is evaluated. If the document is too large, it is clipped at the border of the printing area.</li> <li>Similar to NOSCL (P4)</li> </ul>

..... *To be continued*

## scaleMode (P5), Continuation

Continuation:

values, part 2

Value	Description
fillFit	<ul style="list-style-type: none"> <li>Only the printable area is used. The document is scaled down accordingly.</li> <li>Document that are too small are scaled up.</li> <li>The document is not clipped.</li> </ul>
fill	<ul style="list-style-type: none"> <li>The complete format size is used for the document. The non-printable borders are clipped.</li> <li>Documents that are too large are scaled down to the largest available target format.</li> <li>Document that are too small are scaled up.</li> </ul>
noScale	<ul style="list-style-type: none"> <li>It is not attempted to scale or clip the document even if a PPD file has been specified for the printer.</li> <li>The seal-convert-pdfscale service is not called in this case.</li> </ul>


Default is fitMediaSize.

default

→ *mediaSize (P5)*, page 109

→ *scaleFactor (P5)*, page 149

→ *PLS\_SCALE\_TYPE (P4)*, page 152

 related parameters

## PLS\_SCALE\_TYPE (P4)

purpose

PLS\_SCALE\_TYPE specifies the scaling type of a job.

type



The job parameter is optional.

job type

The job parameter is valid for single jobs and set collations.

values

You can specify the following values:

Value	Description
/DINSCL	<ul style="list-style-type: none"> <li>Documents in the DIN format can be output on single sheets of the same format in full scale (1:1) even if the representation area of the output device is smaller. The document is output in full scale onto the sheet. The borders of the documents which cannot be addressed by the hardware of the output device are clipped.</li> <li>With drawings having non-DIN format, the borders of the document are clipped in the same way.</li> </ul> <p> hint - tolerance borders: However, both with DIN format documents and other document, the DIN scaling is only used if the tolerance limits are not exceeded, see DINSCL_TOLERANCE. Otherwise, the maximum scaling is used.</p> <p> reference - DINSCL_TOLERANCE: → [NETDOME_TEC]</p>
/INTSCL	<ul style="list-style-type: none"> <li>The document is scaled by the factor 1/2, 1/3, 1/4 and so on; this results in the largest area that can be completely printed on the output device.</li> </ul>
/MAXSCL	<ul style="list-style-type: none"> <li>The drawing is scaled down to such an extent that it just can be output completely.</li> </ul>
/NOSCAL	<ul style="list-style-type: none"> <li>The scaling factor PLS_PLOTSCALE is evaluated. If the document is too large, it is clipped at the border of the printing area.</li> </ul>

..... To be continued




## PLS\_SCALE\_TYPE (P4), Continuation

.....  
Default is /DINSCL.

default

.....  
→ *PLS\_PLOTSIZE (P4)*, page 134

→ *PLS\_PLOTSCALE (P4)*, page 133  
.....


 related pa-  
rameters

## PLS\_SCRNODE (P4)

purpose	PLS_SCRNODE specifies the name of the current server.
type	The job parameter is mandatory.
job type	The job parameter is valid for single jobs and set collations.
values	The value is specified as a string with up to 64 characters.
default	There is no default.

## (PLS\_)SECUREPRINT (P4, P5)


.....  
 (PLS\_)SECUREPRINT contains the password that the user has to specify at the output device in order to output the job. purpose  
 .....

- (PLS\_)SECUREPRINT is only taken into account unless the (PLS\_)ENABLE\_SECUREPRINT job parameter has been set to N.  hints
  - The evaluation of (PLS\_)ENABLE\_SECUREPRINT and (PLS\_)SECUREPRINT depend on the support by the output device and the driver template. For small format templates, this support is usually given, except for the generic templates for example.
- .....


The job parameter is optional. type  
 .....

The job parameter is valid for single jobs. job type  
 .....

The value is specified as a string. values  
 .....

The rules which apply for the password, for example, if only digits are allowed or the maximal length of the password, depend on the specific output device!  hint - device-dependent  
 .....

There is no default, that means no password is set. default  
 .....

→ (PLS\_)ENABLE\_SECUREPRINT (P4, P5), page 74  related parameters  
 .....

## PLS\_SENDER (P4)

purpose

PLS\_SENDER specifies the e-mail address of the sender.



hints

- PLS\_SENDER is only evaluated if the output type is set to MAIL.
- In the Web Portal, PLS\_SENDER is used as generator (owner) of the share with the automatic generation of shares.

type

The job parameter is mandatory.

job type

The job parameter is valid for single jobs.

values

The value is specified as a string.

default

There is no default.



related parameters

- *PLS\_RECEIVER (P4)*, page 144
- *PLS\_RECEIVER\_CC (P4)*, page 146
- *PLS\_RECEIVER\_BCC (P4)*, page 145
- *PLS\_MAIL\_MESSAGE (P4)*, page 98
- *PLS\_SUBJECT (P4)*, page 173

## PLS\_SET\_COPY (P4)

PLS\_SET\_COPY specifies the number of copies of the set collation.

purpose

- The PLS\_PLOTCOPY job parameter for single jobs is evaluated for each set member additionally.
- PLS\_SET\_COPY is only evaluated if LICENSE\SETCOLL\_OPTION in plossys.cfg is set to Y.

 hints

The job parameter is optional.

type

The job parameter is valid for set collations.

job type

The value is specified as an integer.


values

- If the value of the job parameter is set to 0, no additional copy of the set collation is output, that means, only one copy of the set collation is output.
- If the value of the job parameter is less than 0 or more than 99, the default is used.

Default is 0.

default

→ (PLS\_)PLOTCOPY (P4, P5), page 126

 related parameters

## PLS\_SET\_MEMBER\_NAME (P4)

purpose

PLS\_SET\_MEMBER\_NAME specifies the identification of the job mapped to the set collation.

 hints

- The number of the PLS\_SET\_MEMBER\_NAME job parameter has to correspond to the number determined by PLS\_SET\_NUMBER.
- The single jobs whose job IDs are listed here also have to have the PLS\_SET\_NAME job parameter containing the name of the set collation.

type

The job parameter is mandatory.

job type


The job parameter is valid for set collations.

values

The value is specified as a string with up to 80 characters.

default

There is no default.

 related parameters

→ *PLS\_SET\_COPY (P4)*, page 157

→ *PLS\_SET\_NAME (P4)*, page 159

## PLS\_SET\_NAME (P4)

PLS\_SET\_NAME specifies the name of the set collation.

purpose

- If a single job is part of a set collation, it also has to have the job parameter with the name of the set collation.
- Additionally, the value of the PLS\_PLOTID job parameter of the single job has to appear as a value of PLS\_SET\_MEMBER\_NAME in the related set collation.
- In the Web Portal, PLS\_SET\_NAME is used as name of the share with the automatic generation of shares.

 hints

The job parameter is mandatory.

type

The job parameter is valid for single jobs and set collations.

job type

The value is specified as a string with up to 80 characters.


values

There is no default.

default

→ *PLS\_SET\_MEMBER\_NAME (P4)*, page 158

→ *(PLS\_)PLOTID (P4, P5)*, page 128

 related parameters

## PLS\_SET\_NUMBER (P4)

purpose

PLS\_SET\_NUMBER specifies the number of single jobs in a set collation.



hints

- The value of the PLS\_SET\_NUMBER job parameter has to match the value of the PLS\_SET\_MEMBER\_NAME job parameter.
- PLS\_SET\_NUMBER is only evaluated if the set collation processing is active.

type

The job parameter is mandatory.

job type

The job parameter is valid for set collations.

values

The value is specified as an integer in the range 1 to 3000.

default

There is no default.



related parameters

→ *PLS\_SET\_MEMBER\_NAME (P4)*, page 158



## (PLS\_)SORT (P4, P5)

.....  
 (PLS\_)SORT specifies if the documents of the job are sorted into different output trays or belts. purpose

- .....
- The (PLS\_)SORT\_TYPE job parameter specifies the output tray or belt.
  - (PLS\_)SORT is only evaluated if the output device has a controllable sorting device.



.....  
 The job parameter is optional. type


.....  
 The job parameter is valid for single jobs. job type

.....  
 The value is specified as a Boolean: values

- Y  
   The document will be sorted.
- N  
   The document will not be sorted.

.....  
 There is no default. default

.....  
 → (PLS\_)SORT\_TYPE (P4, P5), page 162



## (PLS\_)SORT\_TYPE (P4, P5)

purpose

The (PLS\_)SORT\_TYPE job parameter specifies the output tray or belt into which the documents of the job are output.

 hints

- In PLOSSYS 4, the sorting types are specified in the following file:  
server\plotserv\plotter\fold\_sorttypes.cfg
- The output device has to have a controllable sorting device and support the passed values.
- With large formats, (PLS\_)SORT\_TYPE is only evaluated if (PLS\_)SORT is set to Y.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs.

values for large format

In PLOSSYS 4, you can specify the following values for large formats:

Value	Description
Band1	First output tray or belt
Band2	Second output tray or belt
Band3	Third output tray or belt
Stacker	Stacker unit

values for small format

In PLOSSYS 4 and PLOSSYS 5, you can specify the following values for small formats:

Value	Description
Left	Left output tray
Right	Right output tray
Upper	Upper output tray
Center	Center output tray
SideUpper	Upper output tray at the finisher
SideMiddle	Center output tray at the finisher
SideLower	Lower output tray at the finisher


..... To be continued

## (PLS\_)SORT\_TYPE (P4, P5), Continuation

.....  
There is no default.

default

.....  
→ (PLS\_)SORT (P4, P5), page 161

 related pa-  
rameters

## PLS\_SPLITTYPE (P4)

purpose

.....  
PLS\_SPLITTYPE specifies the splitting of the documents of a job.  
.....

 hint

.....  
Documents in large formats are split in several smaller documents and can be output at output devices with a smaller printing area without scaling.  
.....

type

.....  
The job parameter is optional.  
.....

job type


.....  
The job parameter is valid for single jobs.  
.....

*To be continued*

## PLS\_SPLITTYPE (P4), Continuation

You can specify the following values:

values

Value	Description
NOSPLIT	The document will not be split.
DIN	<p>The document will be split according to the DIN standard.</p> <p> hint - landscape/portrait:</p> <p>This standard only applies to landscape documents.</p> <p>With portrait documents, the splitting is not specified. With available DIN A0 and DIN A1 format, for example landscape documents smaller than 594 mm and longer than 841 are split into DIN A1 parts, larger documents into DIN A0 parts.</p> <p>The parts have an overlapping area, whose size is configurable. The overlapping areas in x and y direction are set in <code>plossys.cfg</code> in the correspondent output device section by the <code>SPLIT_X_OVL</code> and <code>SPLIT_Y_OVL</code> keywords.</p>
XY_NO_OVERLAP	The document is split without overlapping in x and y direction. The parts are as large as the largest paper format on the output device.
Y_SCALE_X_SPLIT	The document is scaled in Y direction as long as the documents fits to the largest available media. To avoid distortion, a scaling in X direction with the same scaling factor is executed afterwards. If the document is too large for the medium in X direction, it will be split with in this direction with overlapping.

Default is NOSPLIT.

default

## PLS\_SRCAPPL (P4)

purpose

PLS\_SRCAPPL specifies an external program call executed when the job gets a specified job status.

 hints

- The job status is specified by the PLS\_CALL\_CONDITIONS job parameter.
- The job parameter is specified in the [SYSTEM] section of plossys.cfg.
- The external program call can only be executed if the correspondent privileges are set.

type

The job parameter is mandatory.

job type


The job parameter is valid for single jobs and set collations.

values

The value is specified as a string with up to 255 characters.

default

There is no default.

 related parameters

→ *PLS\_CALL\_CONDITIONS (P4)*, page 53

## PLS\_STAMP\_0 (\_n) (P4)

PLS\_STAMP\_0 to PLS\_STAMP\_n specify the texts which are output as stamps on the job. Additionally, you can specify the name of a specific stamp layout file.

purpose

- The position and the appearance of the stamp can be configured.
- The text can be specified in a text file. Unless the specified text file is found, the default text file, `server\plotserv\generic.stp`, is used.
- In the stamp texts, you can specify PLOSSYS 4-specific variables such as `$PLS_PLOTTER` and environment variables such as `%USERNAME%`.
- The maximum of possible stamps is specified in the `PLS_STAMP_MAX` environment variable, see `[STAMP_USR]`.

 hints

The job parameter is optional.

type

The job parameter is valid for single jobs.

job type

The value is specified as a string with up to 237 characters.

values

A specific stamp layout file is specified at the beginning of the value and enclosed by \$:

```
$layoutfilename$stamp_text
```

In the context of the specific stamp layout file, the following bugs are known:

- If you specify a specific stamp layout file in `PLS_STAMP_0`, the configuration contained in this file is used for all stamps.
- If you specify a specific stamp layout file in `PLS_STAMP_n` with `n` greater than 0, this is used for this stamp only. However, not the configuration of stamp `n` is used but that of stamp 0.

 hint - known bugs

There is no default.

default

*To be continued*

## PLS\_STAMP\_0 (\_n) (P4), Continuation

---

### examples

The Test text is output as stamp 0:

```
$ PLS_STAMP_0 == "Test"
```

The text1 text is output as stamp 1 applying the layout specified in the layout\_stamp1.stp stamp layout file:

```
$ PLS_STAMP_1 == "$layout_stamp1.stp$text1"
```

The value of the USERNAME environment variable is output as stamp 2.

```
$ PLS_STAMP_2 == "%USERNAME%"
```

The value of the PLOSSYS 4-specific variable PLS\_PLOTTER is output as stamp 3:

```
$ PLS_STAMP_3 == "$PLS_PLOTTER"
```

---

### reference

For a detailed description of the text and graphic stamps, refer to:

→ [STAMP\_USR]

---



## (PLS\_)STAPLE (P4, P5)

.....  
 (PLS\_)STAPLE specifies if the documents of the jobs are stapled.  
 .....

purpose

.....  
 The staple type is specified with the (PLS\_)STAPLE\_TYPE job parameter.  
 .....

 hint

.....  
 The job parameter is optional.  
 .....

type

.....  
 The job parameter is valid for single jobs and set collations.  
 .....

job type

.....  
 You can specify the following values:  
 .....

values


Value	Description
Y	The documents are stapled according to the settings of the (PLS_)STAPLE_TYPE job parameter.
N	The document is not stapled.
any value (except of N)	The documents are stapled according to the settings of the (PLS_)STAPLE_TYPE job parameter.

.....  
 There is no default.  
 .....

default

.....  
 → (PLS\_)STAPLE\_TYPE (P4, P5), page 170

→ (PLS\_)BOOKLET (P4, P5), page 52  
 .....

 related parameters

## (PLS\_)STAPLE\_TYPE (P4, P5)

purpose

(PLS\_)STAPLE\_TYPE specifies the position and the number of the stapling.



hints

- In PLOSSYS 4, the staple type is specified in the following file:  
server\plotserv\plotter\fold\_sorttypes.cfg
- Possible staple types depend on the ability of the output device.

type


The job parameter is mandatory for set collation.

job type

The job parameter is valid for single jobs and set collations.

values

You can specify the following values:

Value	Description
OneUpLeft	Once at the upper left corner
OneBottomLeft	Once at the lower left corner
OneUpRight	Once at the upper right corner
OneBottomRight	Once at the lower right corner
TwoLeft	Twice at the upper left corner
TwoRight	Twice at the lower left corner
TwoBottom	Twice at the lower corner
TwoUp	Twice at the upper corner
Booklet	As booklet  hint - obsolete: Booklet with (PLS_)STAPLE_TYPE has been replaced by (PLS_)BOOKLET, but is still supported due to compatibility reasons.

default

There is no default. If (PLS\_)STAPLE is set to Y, the default is OneUpLeft.



related parameters

→ (PLS\_)BOOKLET (P4, P5), page 52

→ (PLS\_)STAPLE (P4, P5), page 169

## PLS\_START\_TIME (P4)

.....  
PLS\_START\_TIME specifies the time when the output of the job is started. purpose

.....  
The job parameter is optional. type

.....  
The job parameter is valid for single jobs and set collations. job type

.....  
The value is specified as a string up to 19 characters in the following format: values

- dd.mm.jjjj HH:MM:SS

.....  
By default, the job is output according to its position in the output queue. default  
.....

## PLS\_STATISTIC\_0 (\_2) (P4)

purpose

.....  
PLS\_STATISTIC\_0 (\_2) specifies the texts output to the statistic file.  
.....

 hint

.....  
The format of the statistic file is specified in plossys.cfg.  
.....

type

.....  
The job parameter is optional.  
.....

job type

.....  
The job parameter is valid for single jobs.  
.....

values

.....  
The value is specified as a string with up to 20 characters.  
.....

default

.....  
There is no default.  
.....

## PLS\_SUBJECT (P4)

PLS\_SUBJECT specifies the subject line of the e-mail.

purpose

- PLS\_SUBJECT is only evaluated if the output type is set to MAIL.
- If the PLS\_SUBJECT job parameter is missing in the header, the value of PLS\_PLOTID is used as subject of the e-mail.
- In the Web Portal, PLS\_SUBJECT is used as description of the share with the automatic generation of shares.

 hints

The job parameter is mandatory.

type

The job parameter is valid for single jobs.

job type

The value is specified as a string with up to 14 characters.

values

Default is PLS\_PLOTID.


default

→ *PLS\_RECEIVER (P4)*, page 144

→ *PLS\_RECEIVER\_CC (P4)*, page 146

→ *PLS\_RECEIVER\_BCC (P4)*, page 145

→ *PLS\_SENDER (P4)*, page 156

 related parameters

## PLS\_TEXTLINEWIDTH (P4)

purpose

PLS\_TEXTLINEWIDTH specifies the nominal line width in meters.



hints

- The value is multiplied by the text line width factor specified in the GKS metafile by an escape function.
- The result is the text line width to be output.

type

The job parameter is optional.

job type

The job parameter is valid for single jobs.

values

The value is specified as a float with up to three digits before and six digits after the decimal point in meters.

default

Default is 0.01.

## (PLS\_)TRAY\_1 (\_n) (P4, P5)

(PLS\_)TRAY\_1 (\_n) specifies the tray for the output.

purpose

- To each page of a multi-page document, an explicit tray can be assigned by setting the variable with the correspondent number: (PLS\_)TRAY\_1 for the first page, (PLS\_)TRAY\_2 for the second page and so on.
- Unless a value is specified for a page, the value specified last is used.
- If for none of the pages a value is specified, the default is used by PLOSSYS 4.



hints

The PAPER\_SELECT setting at the output device determines if (PLS\_)TRAY\_1 (\_n) is evaluated. For more information, refer to → *Job on a Specific Medium (P4, P5)*, page 27.



reference

The job parameter is optional.

type

The job parameter is valid for single jobs and set collations.

job type

For PLOSSYS 4, you can specify the following values:

values PLOSSYS 4

Value	Description
INTRAYAUTO	PLOSSYS 4 request the appropriate tray from the output device according to the output size and the medium selected via (PLS_)PLOT PAPER.
INTRAYMANUAL	PLOSSYS 4 requests the tray from the output device for which the MANUAL type is specified.
INTRAYn	PLOSSYS 4 requests the specified tray from the output device with the number <i>n</i> .



For PLOSSYS 5, you can specify the following values:

values PLOSSYS 5

Value	Description
INTRAYn	PLOSSYS 5 passes the tray with the number <i>n</i> to the output device.
<i>media_type</i>	PLOSSYS 5 passes the media type to the output device.

*To be continued*


## (PLS\_)TRAY\_1 (\_n) (P4, P5), Continuation

additional	<p>Additionally, the values can be specified that can be specified with (PLS_)PLOT-PAPER, for example, SP1.</p>
default	<p>Default is INTRAYAUTO.</p>
relevant key- words	<p>In this context, the following keywords in plossys.cfg are relevant in PLOSSYS 4:</p>
 reference	<p>→ <i>ASK_PAPER</i>, [NETDOME_TEC] → <i>PAPER_SELECT</i>, [NETDOME_TEC]</p>
 related pa- rameters	<p>→ (PLS_)PLOTPAPER (P4, P5), page 130</p>



## PLS\_USEMETA (P4)

PLS\_USEMETA specifies if the values specified via the PLS\_META\_X job parameter are set as metadata in the PDF/A file. purpose

PLS\_USEMETA is only evaluated for the PDF/A processing by the output driver only.  hint

The job parameter is optional. type


The job parameter is valid for single jobs. job type

The value is specified as a Boolean: values

- Y  
The metadata is set in the PDF/A file corresponding to the PLS\_META\_X job parameter.
- N  
The metadata is not set.

Default is N. default

→ *PLS\_META\_n (P4)*, page 110

 related parameters

## PLS\_USERGROUP (P4)

purpose

PLS\_USERGROUP specifies the user group which is assigned to the job.

 hint

User groups can be allowed or forbidden for certain output devices.

type

The job parameter is mandatory.

job type


The job parameter is valid for single jobs and set collations.

values

The value is specified as a string with up to 256 characters.

default

There is no default.

 related parameters

→ *(PLS\_)USERNAME (P4, P5)*, page 179

## (PLS\_)USERNAME (P4, P5)

.....  
(PLS\_)USERNAME specifies the user on the respective server.  
.....

purpose

In PLOSSYS 5, (PLS\_)USERNAME is passed to the userName job parameter. Further sources for userName are:



- Field u in the LPR protocol
  - Standard IPP attribute requesting-user-name
- .....

The job parameter is mandatory.

type

.....  
The job parameter is valid for single jobs and set collations.  
.....

job type


.....  
The value is specified as a string with up to 64 characters.  
.....

values

.....  
There is no default.  
.....

default

.....  
→ *PLS\_USERGROUP (P4)*, page 178  
.....

 related parameters

## PLS\_WINDOW (P4)

### purpose

PLS\_WINDOWS specifies the cropped window which is considered at the output of the job.



### hints

- This clipping can be used for any output job types.
- The cropped window will be positioned on the left bottom corner of the paper.
- If the point  $x_{min}$   $y_{min}$  is larger than  $x_{max}$   $y_{max}$ , then  $x_{min}$   $y_{min}$  will be set to 0 automatically.
- If the point  $x_{max}$   $y_{max}$  is outside the job,  $x_{max}$   $y_{max}$  is set to the largest possible value.

### type

The job parameter is optional.

### job type

The job parameter is valid for single jobs.

### values

The values are specified as four float values. The values are separated by blanks. The area is specified in meters.

- $XMIN$   $YMIN$   $XMAX$   $YMAX$

### default

Default is 0.0 0.0 0.0 0.0.



### related parameters

→ *PLS\_WINDOW\_PAGENUMBER (P4)*, page 181

→ *PLS\_CROP (P4)*, page 62

## PLS\_WINDOW\_PAGENUMBER (P4)

.....  
 PLS\_WINDOW\_PAGENUMBER specifies the cropped window for each page for multi-  
 page files. purpose

.....  
 The job parameter is optional. type

.....  
 The job parameter is valid for single jobs. job type

.....  
 The values are specified as four float values. The values are separated by blanks. values  
 The area is specified in meters.

- XMIN YMIN XMAX YMAX

.....  
 Default is 0.0 0.0 0.0 0.0. default


.....  
 → PLS\_WINDOW (P4), page 180

→ (PLS\_)DUPLEX (P4, P5), page 72

→ PLS\_ONLYFIRSTSTP (P4), page 116

→ PLS\_DIFBACKSTP (P4), page 70

→ PLS\_PAGES (P4), page 119  
 .....

 related pa-  
rameters

## SEAL\_CODEPAGE (P4)

### purpose

SEAL\_CODEPAGE specifies the character encoding of the job.



### hints

- If SEAL\_CODEPAGE is set to UTF-8, the job is processed as a Unicode job.
- Unless the SEAL\_CODEPAGE is set, LATIN1 is set as character encoding via the SEAL\_CODEPAGE environment variable.
- When processing the job, the \$SEAL\_CODEPAGE job parameter is always set to the value UTF-8 due to PLOSSYS 4 always works with UTF-8 as internal character encoding.
- The conversion to UTF-8 is done automatically.
- The original encoding is saved in the SEAL\_ORIGCODEPAGE job parameter.

### type

The job parameter is optional.

### job type

The job parameter is valid for single jobs.

### values

The value is specified as a string with up to 14 characters.

### default

There is no default.

The default is set by the SEAL\_CODEPAGE environment variable. By default, the variable is set to Latin1.



### reference

For a list of all supported character encodings which can be displayed according to UTF-8, refer to:

→ *Supported Character Encodings*, page 184



### related parameters

→ *SEAL\_ORIGCODEPAGE (P4)*, page 183

## SEAL\_ORIGCODEPAGE (P4)

.....  
 SEAL\_ORIGCODEPAGE specifies the original encoding of the job.  
 .....

purpose

.....  
 SEAL\_ORIGCODEPAGE is set by PLOSSYS 4.  
 .....

 hint

.....  
 The job parameter is optional.  
 .....

type


.....  
 The job parameter is valid for single jobs.  
 .....

job type

.....  
 The value is specified as a string with up to 14 characters.  
 .....

values

.....  
 For a list of all supported character encodings which can be displayed according to UTF-8, refer to:


 related topics

.....  
 → *Supported Character Encodings*, page 184  
 .....

.....  
 There is no default.  
 .....

default

.....  
 → *SEAL\_CODEPAGE (P4)*, page 182  
 .....

 related parameters

## Appendix A Supported Character Encodings

### PLOSSYS 4

The following character encodings are supported as input formats:

Character Encoding	Character Encoding	Character Encoding	Character Encoding
7bit-jis	cp857	ISO-10646-1	MacCentralEur-Roman
AdobeSymbol	cp860	ISO-2022-jp-3	MacCroatian
AdobeZdingbat	cp861	ISO-2022-jp	MacDingbats
ascii-ctrl	cp862	ISO-2022-jp-1	MacRomanian
big5-eten	cp863	ISO-2022-kr	MacRumanian
big5ext	cp864	ISO-646-US	MacSami
big5-hkscs	cp865	ISO-8859-1	MIME-B
big5plus	cp866	ISO-8859-10	MIME-Header
cccii	cp869	ISO-8859-11	MIME-Q
cp1006	cp874	ISO-8859-13	N.America (ASCII)
cp1026	cp875	ISO-8859-14	null Special Encoding
cp1047	cp878	ISO-8859-15	posix-bc
cp1250	cp932	ISO-8859-16	shiftjisx0123
cp1251	cp936	ISO-8859-2	symbol
cp1252	cp949	ISO-8859-3	UCS-2BE
cp1253	Cyrillics	ISO-8859-4	UCS-2LE
cp1254	dingbats	ISO-8859-5	US-ascii
cp1255	euc-cn	ISO-8859-6	UTF-16
cp1256	euc-jisx0213	ISO-8859-7	UTF-16BE
cp1257	euc-jp	ISO-8859-8	UTF-16LE
cp1258	euc-kr	ISO-8859-9	UTF-32
cp437	euc-tw	ISO-ir-165	UTF-32BE
cp500	gb12345-raw	jis0201-raw	UTF-32LE
cp737	gb18030	jis0208-raw	UTF-7
cp775	gb2312-raw	jis0212-raw	UTF-8



## Bibliography

---

---

[OPERATOR_TEC]	<i>SEAL Operator</i> , System description, <a href="https://operator.docs.sealsystems.de/">https://operator.docs.sealsystems.de/</a>
[NETDOME_ADDSH_TEC]	<i>PLOSSYS netdome - Additional Sheets</i> , System Description, SEAL Systems
[NETDOME_SETTINGS_TEC]	<i>PLOSSYS netdome Settings</i> , System Description, SEAL Systems
[NETDOME_TEC]	<i>PLOSSYS netdome</i> , System Description, SEAL Systems
[PDFTOOLS_TEC]	<i>PDF Tools</i> , System Description, SEAL Systems
[PLOSSYS_5_TEC]	<i>PLOSSYS 5</i> , System description, <a href="https://plossys-5.docs.sealsystems.de/">https://plossys-5.docs.sealsystems.de/</a>
[STAMP_USR]	<i>Stamping (PLOSSYS netdome, pdfstamp)</i> , User Manual, SEAL Systems

---

## Terminology

The following section explains the most important terms that are used in this documentation. Terms identified by → refer to other terms in this section.

Job	A document that is issued by PLOSSYS 4 or PLOSSYS 5; With PLOSSYS 4, a job is accepted when the following files are copied to the corresponding →Gate directory: <ol style="list-style-type: none"> <li>1. →Graphic file with correct file extension (example: example.hpgl)</li> <li>2. Possibly the →header (example: example.hed)</li> <li>3. Possible additional files such as color and pen tables</li> <li>4. And finally the →trigger file (example: example.rdy)</li> </ol> With PLOSSYS 5, a job is sent to the check-in service via IPP or LPR.
Job input directory	→Gate directory
Job parameter	Setting for processing and outputting a →job
Set collation	Combined set of →output jobs
Output job	→Job
Output device	Device on which the document is output
Output parameter	→Job parameter
Output driver	Program for controlling an →output device
Inscription	→Flagpage
BC-XOM	OMS interface from SAP, which can be used to connect external output management systems such as → PLOSSYS 4 and →PLOSSYS 5 to SAP's spool system.
Check-in service component	of →PLOSSYS 5, which is responsible for accepting output jobs.
Cover sheet	First sheet of a →set collation; it contains information about the job and the documents included in the job. The cover sheet is an →additional sheet.
Default-Header	→Header containing defaults for the →job parameter in →PLOSSYS 4
Printer configuration file	Configuration file in PLOSSYS 4 for →multi-drawers as addition to the configuration in the PLOSSYS 4 configuration file, plossys.cfg
Single job	→Job with one document
Single job header	→Header belonging to a →single job in PLOSSYS 4
Trailer sheet	Last sheet of a →set collation; it contains information about the job and the documents included in the job. The end sheet is an →additional sheet.
Missing sheet	Sheet that is output instead of the original document within a →set collation when the document did not arrive in the system after a timeout. The missing sheet is also called →additional sheet.
Error sheet	Sheet that is output instead of the original sheet when an error occurred while creating the document. The error sheet is an →additional sheet.
Flagpage	Lettering line in the margin of the document
Format converter	Program for converting a document from one graphic format into another
Gate	Job input for PLOSSYS 4; there is a separate gate or converter for each graphic format supported by PLOSSYS 4. It consists of

	<ol style="list-style-type: none"> <li>1. The →gate directory,</li> <li>2. The →gate process and</li> <li>3. The →gate converter.</li> </ol> Special gates: →Maingate
Gate converter	→Format converter called by the →gate process
Gate process	Process in PLOSSYS 4 which converts the image files into another graphic format, and then passes them on to be output
Gate directory	File directory in PLOSSYS 4, into which incoming →jobs are copied
Graphic file	File that contains the graphic information of the document
Header	File in ASCII format that contains items for configuring a →job in PLOSSYS 4
Header item	→Job parameter in PLOSSYS 4
Console	User interface of PLOSSYS 4 in order to administrate jobs and output devices; →PLOSSYS OCON
Maingate	All jobs preprocessed by the other → gates are copied to the maingate directory in PLOSSYS 4 and processing is continued there.
Metafile	File in the →metaformat
Metaformat	Standardized graphic format (for example, GKSM, CGM, TIFF/G4) in PLOSSYS 4
Multi-drawer output device	device with multiple media trays or rolls; configured by a section in the PLOSSYS 4 configuration file, <code>plossys.cfg</code> , in the <code>server/plotserv</code> directory and by a →printer configuration file
PLOSSYS 4	Alternative product name for →PLOSSYS netdome; used in connection with PLOSSYS 5 and in this overarching documentation.
PLOSSYS 5	New version of the output management system from SEAL Systems based on the microservice architecture and specifically designed for cloud operation
PLOSSYS Administrator	Graphical administration interface to →PLOSSYS 5
PLOSSYS netdome	Output management system from SEAL Systems
PLOSSYS OCON	Graphical user interface of →PLOSSYS 4
Pool device	Pseudo output device which combines several →individual printers to a pool and distributes incoming jobs to its individual printers
Preprocessor	→Gate process which usually calls a format converter
Ready file	→trigger file
Set header	File with items for configuring the →set collation in PLOSSYS 4
Set member	→Single job belonging to a →set collation
SEAL Operator	Web-based client framework for various SEAL Systems products (→PLOSSYS 4, →PLOSSYS 5, PLOSSYS@archive, DPF, Web Portal etc.)
Spool file	Final graphic file which is sent to the output device
Stamp	Graphic element which PLOSSYS 4 applies onto the document; not to be confused with the →flagpage
Tray	Output bin of a output device
Trigger file	File by means of which PLOSSYS 4 is informed, that all the data of a →job have been copied to the →gate directory, and that the job can be processed

---

	now
Web Portal	Browser-based application from SEAL Systems for the digital distribution and secure sending of any number of documents and documents of any size; based on →SEAL Operator
Additional sheet	→cover sheet, →trailer sheet, →missing sheet, →error sheet

---

## Abbreviations

---

ASCII	American Standard Code for Information Interchange
BC	Business Connector
C907	CalComp Format 907 (vector format)
CAD	Computer Aided Design
CALS	Computer Aided Acquisition a Logistic Supports
CGM	Computer Graphics Metafile (vector format)
DIN	German Institute of Standardization
GIF	Graphic Interchange Format
GKS	Graphic Kernel System
GKSM	GKS Metafile (vector format)
GKSMR	GKS Metafile in record oriented format
GKSMRW	GKSMR in the case of which the drawing size is taken from the header
GKSMS	GKS Metafile in streamed format
GKSMSW	GKSMS in the case of which the drawing size is taken from the header
HCBS	Host Computer Basic Software
HPGL	Hewlett-Packard Graphic Language (vector format)
HPGL/2	Hewlett-Packard Graphic Language 2 (vector format)
IPP	Internet Printing Protocol
JPEG	Joint Photographic Experts Group
LPR line printer Remote	
OMS	Output Management System
P4	PLOSSYS 4
P5	PLOSSYS 5
PDF	Adobe Portable Document Format
PDF/A	Adobe Portable Document Format (PDF/A standard)
PLOSSYS®	Product family from SEAL Systems
PLOSSYS netdome Settings (PNE)	
PPD	PostScript Printer Description
PS	PostScript
TIFF	Tagged Image File Format
XML	Extensible Markup Language
XOM	Extended Output Management

---

## Keywords

### B

Band1 162  
 Band2 162  
 Band3 162  
 Booklet 170

### C

C907 189  
 Center 162  
 CenterFold 79  
 copies 126

### D

DINA\_Heftrand 79  
 DINA\_Heftstr 79  
 document-name 118

### F

FALLBACK\_xx 27  
 fileName 118

### G

GIF 189  
 GKSMW 189  
 GXCFORMATRULE 109

### J

job.current 24  
 job.orig 24  
 jobName 92, 128  
 job-name 128  
 job-printer-uri 135  
 JPEG 189

### L

Left 162  
 LEFT\_JOB\_SIDE 72  
 LEFT\_SIDE 72  
 LONG\_SIDE 72, 73

### M

mediaSize 109

### O

OneBottomLeft 170  
 OneBottomRight 170  
 OneUpLeft 170  
 OneUpRight 170

### P

Paket210 79  
 PLS\_ACCOUNT\_KEY 46  
 PLS\_AUX\_ABSENDER 47  
 PLS\_AUX\_ABTEILUNG 48  
 PLS\_AUX\_KOSTENSTELLE 49  
 PLS\_AUX\_STANDORT 50  
 PLS\_AUX\_TELEFON 51  
 PLS\_BOOKLET 52  
 PLS\_CALL\_CONDITIONS 53  
 PLS\_CDBAN 54  
 PLS\_CDKUR 55  
 PLS\_COLLATE 56  
 PLS\_CONVERTER\_CFG 57  
 PLS\_COST\_TYPE 58  
 PLS\_COSTCENTER 59  
 PLS\_CREATE\_COVER 60, 66  
 PLS\_CREATE\_TRAILER 61  
 PLS\_CROP 62  
 PLS\_CROP\_MARKS 63  
 PLS\_CRYPT 64  
 PLS\_CRYPT\_OPTIONS 65  
 PLS\_DATA\_0 (\_9) 66  
 PLS\_DEBUG 67  
 PLS\_DELTYPE 68  
 PLS\_DEPARTMENT 69  
 PLS\_DIFBACKSTP 70  
 PLS\_DUMMY\_0 (\_9) 71  
 PLS\_DUPLEX 72  
 PLS\_ENABLE\_SECUREPRINT 37, 74  
 PLS\_EXECNODE 75  
 PLS\_FIXLW 76  
 PLS\_FLAGPAGE 77  
 PLS\_FOLD 78  
 PLS\_FOLD\_TYPE 79  
 PLS\_FORM\_STYLE 80  
 PLS\_GATE\_OUTPUT 81  
 PLS\_GKS\_COLTAB 82  
 PLS\_GRAY 83  
 PLS\_GS\_TIMEOUT 84  
 PLS\_HEADER\_TYPE 85  
 PLS\_HOLD 86  
 PLS\_INFO\_0 (\_9) 87  
 PLS\_INTERNAL\_ID 88  
 PLS\_IPP\_IGNORE\_QUEUE 89  
 PLS\_JOB\_STAT 90  
 PLS\_JOB\_STAT\_MSG 91, 92  
 PLS\_LINEWIDTH 93  
 PLS\_MAIL 94

PLS\_MAIL\_COMPRESS 95  
 PLS\_MAIL\_FILENAME 96  
 PLS\_MAIL\_MERGE\_PDF\_MEMBER 97  
 PLS\_MAIL\_MESSAGE 98  
 PLS\_MAIL\_MESSAGE\_TEXT\_TYPE 99, 113  
 PLS\_MAIL\_SEND\_ATTACHMENT 100  
 PLS\_MAIL\_TEXTFILE 101  
 PLS\_MAIL\_USE\_SET\_HEADER 102  
 PLS\_MAIL\_USE\_TEXTFILE 103  
 PLS\_MAIL\_ZIP 104  
 PLS\_MAIL\_ZIP\_FILENAME 105  
 PLS\_MAIL\_ZIP\_MEMBER 106  
 PLS\_MARKER 107  
 PLS\_MAXMAILSIZE 108  
 PLS\_META\_n 110  
 PLS\_MIRROR 114  
 PLS\_NETTO\_PLOTSIZE 115  
 PLS\_ONLYFIRSTSTP 116  
 PLS\_ORIG\_EXT 117  
 PLS\_ORIG\_NAME 118  
 PLS\_PAGES 119  
 PLS\_PAPER\_OPT 120  
 PLS\_PENTAB 123  
 PLS\_PLOT\_FORMAT 124  
 PLS\_PLOT\_ID 128  
 PLS\_PLOT\_ROTATE 125  
 PLS\_PLOTCOPY 126  
 PLS\_PLOTDATE 127  
 PLS\_PLOTITEM 129  
 PLS\_PLOTPAPER 130  
 PLS\_PLOTPEN 132  
 PLS\_PLOTSCALE 133  
 PLS\_PLOTSIZE 134  
 PLS\_PLOTTYPE 136  
 PLS\_POOLPLOTTER\_ALL 139  
 PLS\_PRINT\_QUALITY 140  
 PLS\_PRIO 141  
 PLS\_PUNCH 142  
 PLS\_PUNCH\_TYPE 143  
 PLS\_RECEIVER 144  
 PLS\_RECEIVER\_BCC 145  
 PLS\_RECEIVER\_CC 146  
 PLS\_ROTATE 147  
 PLS\_SAVE\_SPOOLFILE 148  
 PLS\_SCALE\_TYPE 152  
 PLS\_SCRNODE 154  
 PLS\_SECUREPRINT 37, 155  
 PLS\_SENDER 156  
 PLS\_SET\_COPY 157  
 PLS\_SET\_MEMBER\_NAME 158  
 PLS\_SET\_NAME 159  
 PLS\_SET\_NUMBER 160  
 PLS\_SORT 161  
 PLS\_SORT\_TYPE 162  
 PLS\_SPLITTYPE 164  
 PLS\_SRCAPPL 166  
 PLS\_STAMP\_0 (\_n) 167  
 PLS\_STAPLE 169  
 PLS\_STAPLE\_TYPE 170  
 PLS\_START\_TIME 171  
 PLS\_STATISTIC\_0 (\_2) 172  
 PLS\_SUBJECT 173  
 PLS\_TEXTLINEWIDTH 174  
 PLS\_TRAY\_1 (\_n) 175  
 PLS\_USEMETA 177  
 PLS\_USERGROUP 178  
 PLS\_USERNAME 179  
 PLS\_WINDOW 180  
 PLS\_WINDOW\_pagewidth 181  
 printerName 135

**R**

requesting-user-name 179  
 Right 162

**S**

SAP\_OMS\_S\_COPIES 126  
 SAP\_OMS\_S\_DEVICE 135  
 SAP\_OMS\_S\_FILE 118  
 scaleFactor 149  
 scaleMode 150  
 SEAL\_CODEPAGE 182  
 SEAL\_ORIGCODEPAGE 183  
 seal-attributes 22  
 SHORT\_SIDE 72, 73  
 SideLower 162  
 SideMiddle 162  
 SideUpper 162  
 Stacker 162

**T**

TOP\_JOB\_SIDE 72  
 TOP\_SIDE 72  
 TwoBottom 170  
 TwoLeft 170  
 TwoRight 170  
 TwoUp 170

**U**

Upper 162  
 userName 179

**W**

WIN\_INF\_COPIES 126

Z

ZFold 79



## Index

### A

- additional information 31
  - cost center 31
  - location 31
- additional sheet 29, 188
- ASCII 189

### B

- BC 189
- BC-XOM 186

### C

- CAD 189
- CALS 189
- center folding 79
- CGM 189
- check-in service 186
- console 187
- cover sheet 186
- cover sheet (additional sheet) 29

### D

- database object 24
- default header 186
- DIN 189

### E

- end processing 30
  - booklet output 30
  - fold 30
  - punch 30
  - sort 30
  - staple 30
- error sheet 186
- error sheet (additional sheet) 29

### F

- file name 118
- flagpage 186
- flow 186
- fold type 79
- folding 78
- format 26
- format converter 186

### G

- gate 186
- gate converter 187
- gate directory 187
- gate process 187

- GKS 189
- GKSM 189
- GKSMR 189
- GKSMRW 189
- GKSMS 189
- graphic file 187

### H

- HCBS 189
- header 187
- header item, see job parameter 187
- HPGL 189
- HPGL/2 189

### I

- inscription, see flagpage
- IPP 189
- IPP collection 22

### J

- job 186
- job input directory, see gate directory
- job parameter 186

### L

- line width 26
- LPR 189

### M

- main gate 187
- metafile 187
- metaformat 187
- missing sheet 186
- missing sheet (additional sheet) 29
- multi-drawer 187

### O

- OMS 189
- output device 186
- output driver 186
- output job, see job
- output media 27
- output parameter, see job parameter

### P

- P4 189
- P5 189
- package folding 79
- password 37, 155
- PDF 189

PDF/A 189  
PLOSSYS 189  
PLOSSYS 4 187  
PLOSSYS 5 187  
PLOSSYS Administrator 187  
PLOSSYS OCON 187  
PNE 189  
pool device 187  
PostScript 22  
PPD 189  
PPD file 109, 151  
preprocessor 187  
printer configuration file 186  
priority 20  
PS 189

## R

ready file, see trigger file  
rotation 26

## S

scaling 26  
SEAL MasterDriver 22  
SEAL Operator 187  
set collation 186  
set header 187  
set member 187  
set output 28  
single job 186  
single job header 186  
splitting 26  
spool file 187  
stamp 187  
structure 15  
    set header 17  
    set member 18  
    single job 16

## T

TIFF 189  
trailer sheet 186  
trailer sheet (additional sheet) 29  
tray 187  
trigger file 187

## U

Unicode  
    supported character encodings 184

## W

Web Portal 188

## X

XML 189  
XOM 189

## Z

Z folding 79